

RCCM

0.98

Generated by Doxygen 1.8.13

Contents

1 Namespace Index

1.1 Packages

Here are the packages with brief descriptions (if available):

CameraCalibration	??
PressureCameraTrigger	??
RCCM	??
RCCM.Properties	??
RCCM.UI	??
RepeatabilityTest	??

2 Hierarchical Index

2.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

RCCM.UI.LensCalibrationForm.CalibrationPoint	??
Form	
RCCM.UI.AboutRCCMForm	??
RCCM.UI.CameraSettingsForm	??
RCCM.UI.CoordinateSystemSettingsForm	??
RCCM.UI.LensCalibrationForm	??
RCCM.UI.MotorSettingsForm	??
RCCM.UI.NewMeasurementForm	??
RCCM.UI.NFOVViewForm	??
RCCM.UI.PluginInitializationForm	??
RCCM.UI.RCCMMainForm	??
RCCM.UI.WFOVViewForm	??
RCCM.ICamera	??
RCCM.NFOV	??
RCCM.WFOV	??

RCCM.ICycleCounter	??
RCCM.CycleCounter	??
RCCM.DataqCycleCounter	??
RCCM.IRCCMPlugin	??
CameraCalibration.CameraCalibrationPlugin	??
PressureCameraTrigger.PressureCameraTriggerPlugin	??
RepeatabilityTest.RepeatabilityTestPlugin	??
RCCM.IRCCMPluginActor	??
CameraCalibration.CameraCalibration	??
PressureCameraTrigger.PressureCameraTrigger	??
RepeatabilityTest.RepeatabilityTest	??
RCCM.Logger	??
RCCM.Measurement	??
RCCM.Motor	??
RCCM.TrioStepperMotor	??
RCCM.TrioStepperZMotor	??
RCCM.VirtualMotor	??
RCCM.NFOVLensController	??
ObservableCollection	
RCCM.MeasurementSequence	??
RCCM.PanelView	??
RCCM.RCCMPluginLoader	??
RCCM.RCCMSystem	??
RCCM.Settings	??
RCCM.TestResults	??
RCCM.TrioController	??

3 Class Index

3.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

RCCM.UI.AboutRCCMForm	??
Form for displaying info about program and RCCM team	

RCCM.UI.LensCalibrationForm.CalibrationPoint	Value class for storing the input output pairs of a calibration point	??
CameraCalibration.CameraCalibration	Plugin for calibrating camera by image processing technique	??
CameraCalibration.CameraCalibrationPlugin	Defines parameters for automatic calibration plugin	??
RCCM.UI.CameraSettingsForm	Form for adjusting some camera settings	??
RCCM.UI.CoordinateSystemSettingsForm	Form for modifying coordinate system settings such as offsets and angles	??
RCCM.CycleCounter	Tracks the cycle number of the test. Can be paused and restarted. This is a virtual implementation of ICycleCounter	??
RCCM.DataqCycleCounter	Cycle counter using analog pressure input to get pressure and cycle	??
RCCM.ICamera	Interface defining the basic functionalities of the NFOV and WFOV cameras to allow both cameras to be referenced by the exact same code	??
RCCM.ICycleCounter		??
RCCM.IRCCMPlugin	Interface that plugins must implement to provide identifying information about plugin	??
RCCM.IRCCMPluginActor	Interface that allows plugins to define a function that is called to run them	??
RCCM.UI.LensCalibrationForm	GUI for adjusting NFOV lens focus calibration	??
RCCM.Logger	Helper object for logging debug information with relevant metadata	??
RCCM.Measurement	Class representing a measurement of a crack vertex and RCCM data on when it was taken	??
RCCM.MeasurementSequence		??
RCCM.Motor	Abstract representation of stepper motor. Defines the minimum functions and variables needed to define the motor	??
RCCM.UI.MotorSettingsForm	Form for adjusting settings of individual actuators	??
RCCM.UI.NewMeasurementForm	Form for defining settings for a new MeasurementSequence	??
RCCM.NFOV	Class that handles connecting to and operating NFOV camera (BlackFly	??
RCCM.NFOVLensController	Class for operating Gardasoft controller and focusing both optotune liquid lenses	??

RCCM.UI.NFOVViewForm	Form for displaying NFOV live image and measurement overlay	??
RCCM.PanelView	Object used to draw panel graphic to show location of stages	??
RCCM.UI.PluginInitializationForm	Form for starting plugin and entering inputs	??
PressureCameraTrigger.PressureCameraTrigger	Captures images when trigger pressure is reached	??
PressureCameraTrigger.PressureCameraTriggerPlugin		??
RCCM.UI.RCCMMainForm	The main window of the program from which all hardware initialization and termination is directed	??
RCCM.RCCMPluginLoader	Plugin loading framework from https://code.msdn.microsoft.com/windowsdesktop/creating-a-simple-plugin-b6174b62	??
RCCM.RCCMSystem	Object representing all the hardware and definitions for the RCCM	??
RepeatabilityTest.RepeatabilityTest		??
RepeatabilityTest.RepeatabilityTestPlugin		??
RCCM.Settings	Object representing settings json file	??
RCCM.TestResults	Helper object for plotting test status such as crack lengths and pressure	??
RCCM.TrioController	Class representing Trio stepper motor controller	??
RCCM.TrioStepperMotor	Object representing a physical motor controlled through Trio controller	??
RCCM.TrioStepperZMotor	Actuator controlled through trio controller that adjusts its position based on distance sensor input	??
RCCM.VirtualMotor	Virtual representation of motor for use when motor is not connected	??
RCCM.WFOV	Class representing DMK Z12G445 camera for the RCCM WFOV	??
RCCM.UI.WFOVViewForm	Form for displaying WFOV live image and measurement overlay	??

4 Namespace Documentation

4.1 CameraCalibration Namespace Reference

Classes

- class [CameraCalibration](#)
Plugin for calibrating camera by image processing technique
- class [CameraCalibrationPlugin](#)
Defines parameters for automatic calibration plugin

4.2 PressureCameraTrigger Namespace Reference

Classes

- class [PressureCameraTrigger](#)
Captures images when trigger pressure is reached
- class [PressureCameraTriggerPlugin](#)

4.3 RCCM Namespace Reference

Namespaces

Classes

- class [CycleCounter](#)
Tracks the cycle number of the test. Can be paused and restarted. This is a virtual implementation of [ICycleCounter](#)
- class [DataqCycleCounter](#)
Cycle counter using analog pressure input to get pressure and cycle
- interface [ICamera](#)
Interface defining the basic functionalities of the [NFOV](#) and [WFOV](#) cameras to allow both cameras to be referenced by the exact same code
- interface [ICycleCounter](#)
- interface [IRCCMPlugin](#)
Interface that plugins must implement to provide identifying information about plugin
- interface [IRCCMPluginActor](#)
Interface that allows plugins to define a function that is called to run them
- class [Logger](#)
Helper object for logging debug information with relevant metadata
- class [Measurement](#)
Class representing a measurement of a crack vertex and [RCCM](#) data on when it was taken
- class [MeasurementSequence](#)
- class [Motor](#)
Abstract representation of stepper motor. Defines the minimum functions and variables needed to define the motor
- class [NFOV](#)
Class that handles connecting to and operating [NFOV](#) camera ([BlackFly](#)
- class [NFOVLensController](#)
Class for operating Gardasoft controller and focusing both optotune liquid lenses
- class [PanelView](#)
Object used to draw panel graphic to show location of stages
- class **Program**
Main program
- class [RCCMPluginLoader](#)

- Plugin loading framework from <https://code.msdn.microsoft.com/windowsdesktop/Creating-a-simple-plugi>
- class [RCCMSystem](#)
 Object representing all the hardware and definitions for the [RCCM](#)
- class [Settings](#)
 Object representing settings json file
- class [TestResults](#)
 Helper object for plotting test status such as crack lengths and pressure
- class [TrioController](#)
 Class representing Trio stepper motor controller
- class [TrioStepperMotor](#)
 Object representing a physical motor controlled through Trio controller
- class [TrioStepperZMotor](#)
 Actuator controlled through trio controller that adjusts its position based on distance sensor input
- class [VirtualMotor](#)
 Virtual representation of motor for use when motor is not connected
- class [WFOV](#)
 Class representing DMK Z12G445 camera for the [RCCM WFOV](#)

Enumerations

- enum [RCCMStage](#) { **RCCM1**, **RCCM2**, **Coarse**, **None** }
 Enum representing the two sets of fine axes
- enum [MeasurementMode](#) { **Projection**, **Tip**, **Total** }
 Enum representing different methods for calculating crack length
- enum [CoordinateSystem](#) { **Global**, **Local** }
 Enum representing different global (FASTER facility) vs local (pabel) coordinate system

4.3.1 Enumeration Type Documentation

4.3.1.1 CoordinateSystem

```
enum RCCM.CoordinateSystem [strong]
```

Enum representing different global (FASTER facility) vs local (pabel) coordinate system

4.3.1.2 MeasurementMode

```
enum RCCM.MeasurementMode [strong]
```

Enum representing different methods for calculating crack length

4.3.1.3 RCCMStage

```
enum RCCM.RCCMStage [strong]
```

Enum representing the two sets of fine axes

4.4 RCCM.Properties Namespace Reference

Classes

- class **Resources**
A strongly-typed resource class, for looking up localized strings, etc.
- class **Settings**

4.5 RCCM.UI Namespace Reference

Classes

- class [AboutRCCMForm](#)
Form for displaying info about program and [RCCM](#) team
- class [CameraSettingsForm](#)
Form for adjusting some camera settings
- class [CoordinateSystemSettingsForm](#)
Form for modifying coordinate system settings such as offsets and angles
- class [LensCalibrationForm](#)
GUI for adjusting [NFOV](#) lens focus calibration
- class [MotorSettingsForm](#)
Form for adjusting settings of individual actuators
- class [NewMeasurementForm](#)
Form for defining settings for a new [MeasurementSequence](#)
- class [NFOVViewForm](#)
Form for displaying [NFOV](#) live image and measurement overlay
- class [PluginInitializationForm](#)
Form for starting plugin and entering inputs
- class [RCCMMainForm](#)
The main window of the program from which all hardware initialization and termination is directed
- class [WFOVViewForm](#)
Form for displaying [WFOV](#) live image and measurement overlay

4.6 RepeatabilityTest Namespace Reference

Classes


- class [RepeatabilityTest](#)
- class [RepeatabilityTestPlugin](#)

5 Class Documentation

5.1 RCCM.UI.AboutRCCMForm Class Reference

Form for displaying info about program and [RCCM](#) team

Inheritance diagram for RCCM.UI.AboutRCCMForm:



Protected Member Functions

- override void [Dispose](#) (bool disposing)
Clean up any resources being used.

5.1.1 Detailed Description

Form for displaying info about program and [RCCM](#) team

5.1.2 Member Function Documentation

5.1.2.1 Dispose()

```
override void RCCM.UI.AboutRCCMForm.Dispose (
    bool disposing ) [protected]
```

Clean up any resources being used.

Parameters

<i>disposing</i>	true if managed resources should be disposed; otherwise, false.
------------------	---

The documentation for this class was generated from the following files:

- [RCCM/UI/AboutRCCMForm.cs](#)
- [RCCM/UI/AboutRCCMForm.Designer.cs](#)

5.2 RCCM.UI.LensCalibrationForm.CalibrationPoint Class Reference

Value class for storing the input output pairs of a calibration point

Public Member Functions

- **CalibrationPoint** (double i, double f)

Properties

- double **InputPower** [get, set]
- double **FocalPower** [get, set]

5.2.1 Detailed Description

Value class for storing the input output pairs of a calibration point


The documentation for this class was generated from the following file:

- [RCCM/UI/LensCalibrationForm.cs](#)

5.3 CameraCalibration.CameraCalibration Class Reference

Plugin for calibrating camera by image processing technique

Inheritance diagram for CameraCalibration.CameraCalibration:



Public Member Functions

- [CameraCalibration](#) ([RCCMSystem](#) rccm, Dictionary< string, string > parameters)
Create plugin actor from parameter strings
- void [Run](#) ()
Moves actuators and captures images for calibration
- void [Stop](#) ()

Static Public Member Functions

- static double **SumSquaresResidual** (double[] x, double[,] y, double m, double b)
- static double [SumSquaresTotal](#) (double[,] y)
Calculate total error from mean
- static double [FindLinearLeastSquaresFit](#) (double[] x, double[,] y, out double m, out double b)
Find the least squares linear fit.

Protected Attributes

- readonly [RCCMSystem](#) **rccm**
- readonly [ICamera](#) **camera**
- string **path**
- readonly [Motor](#) **xMotor**
- readonly [Motor](#) **yMotor**
- Thread **testThread**

Properties

- bool **Running** [get]

5.3.1 Detailed Description

Plugin for calibrating camera by image processing technique

5.3.2 Constructor & Destructor Documentation

5.3.2.1 CameraCalibration()

```

CameraCalibration.CameraCalibration.CameraCalibration (
    RCCMSystem rccm,
    Dictionary< string, string > parameters )
  
```

Create plugin actor from parameter strings

Parameters

<i>rccm</i>	Reference to RCCM object
<i>parameters</i>	Map of test parameters to values

5.3.3 Member Function Documentation**5.3.3.1 FindLinearLeastSquaresFit()**

```
static double CameraCalibration.CameraCalibration.FindLinearLeastSquaresFit (
    double [] x,
    double y[,],
    out double m,
    out double b ) [static]
```

Find the least squares linear fit.

Parameters

<i>x</i>	x values of fit data points
<i>y</i>	y values of fit data points
<i>m</i>	slope of best fit line
<i>b</i>	y-intercept

Returns

Total error from best fit line

5.3.3.2 Run()

```
void CameraCalibration.CameraCalibration.Run ( )
```

Moves actuators and captures images for calibration

summary> Stops the test by interrupting the test thread /summary>

Implements [RCCM.IRCCMPluginActor](#).

5.3.3.3 Stop()

```
void CameraCalibration.CameraCalibration.Stop ( )
```

summary> Return the error squared. /summary>

Implements [RCCM.IRCCMPluginActor](#).

5.3.3.4 SumSquaresTotal()

```
static double CameraCalibration.CameraCalibration.SumSquaresTotal (  
    double y[, ] ) [static]
```

Calculate total error from mean

Parameters

<i>y</i>	<i>y</i> values of linear fit
----------	-------------------------------

Returns

Total error from mean


The documentation for this class was generated from the following file:

- RCCM/Plugins/CameraCalibration/CameraCalibration.cs

5.4 CameraCalibration.CameraCalibrationPlugin Class Reference

Defines parameters for automatic calibration plugin

Inheritance diagram for CameraCalibration.CameraCalibrationPlugin:

**Public Member Functions**

- [IRCCMPluginActor Instance](#) ([RCCMSystem](#) rccm, Dictionary< string, string > parameters)
Create plugin with given test parameters

Properties

- string [Name](#) [get]
Publicly visible plugin name
- string [] [Params](#) [get]
Test has one parameter - name of camera being calibrated

5.4.1 Detailed Description

Defines parameters for automatic calibration plugin

5.4.2 Member Function Documentation**5.4.2.1 Instance()**

```

IRCCMPluginActor CameraCalibration.CameraCalibrationPlugin.Instance (
    RCCMSystem rccm,
    Dictionary< string, string > parameters )
  
```

Create plugin with given test parameters

Parameters

<i>rccm</i>	
<i>parameters</i>	User entered test parameters

Returns

Implements [RCCM.IRCCMPlugin](#).

5.4.3 Property Documentation

5.4.3.1 Name

```
string CameraCalibration.CameraCalibrationPlugin.Name [get]
```

Publicly visible plugin name

5.4.3.2 Params

```
string [] CameraCalibration.CameraCalibrationPlugin.Params [get]
```

Test has one parameter - name of camera being calibrated


The documentation for this class was generated from the following file:

- [RCCM/Plugins/CameraCalibration/CameraCalibrationPlugin.cs](#)

5.5 RCCM.UI.CameraSettingsForm Class Reference

Form for adjusting some camera settings

Inheritance diagram for RCCM.UI.CameraSettingsForm:



Public Member Functions

- [CameraSettingsForm](#) ([RCCMSystem](#) rccm)
Create camera settings form

Protected Member Functions

- override void [Dispose](#) (bool disposing)
Clean up any resources being used.

Protected Attributes

- readonly [RCCMSystem](#) **rccm**

5.5.1 Detailed Description

Form for adjusting some camera settings

5.5.2 Constructor & Destructor Documentation

5.5.2.1 CameraSettingsForm()

```
RCCM.UI.CameraSettingsForm.CameraSettingsForm (
    RCCMSystem rccm )
```

Create camera settings form

Parameters

<i>rccm</i>	Reference to RCCM object
-------------	--

5.5.3 Member Function Documentation

5.5.3.1 Dispose()

```
override void RCCM.UI.CameraSettingsForm.Dispose (
    bool disposing ) [protected]
```

Clean up any resources being used.

Parameters

<i>disposing</i>	true if managed resources should be disposed; otherwise, false.
------------------	---


The documentation for this class was generated from the following files:

- RCCM/UI/CameraSettingsForm.cs
- RCCM/UI/CameraSettingsForm.Designer.cs

5.6 RCCM.UI.CoordinateSystemSettingsForm Class Reference

Form for modifying coordinate system settings such as offsets and angles

Inheritance diagram for RCCM.UI.CoordinateSystemSettingsForm:



Public Member Functions

- [CoordinateSystemSettingsForm](#) ([RCCMSystem](#) rccm)
Open coordinate system form

Protected Member Functions

- override void [Dispose](#) (bool disposing)
Clean up any resources being used.

Protected Attributes

- readonly [RCCMSystem](#) **rccm**

5.6.1 Detailed Description

Form for modifying coordinate system settings such as offsets and angles

5.6.2 Constructor & Destructor Documentation

5.6.2.1 CoordinateSystemSettingsForm()

```
RCCM.UI.CoordinateSystemSettingsForm.CoordinateSystemSettingsForm (
    RCCMSystem rccm )
```

Open coordinate system form

Parameters

<i>rccm</i>	Reference to RCCM object
-------------	--

5.6.3 Member Function Documentation

5.6.3.1 Dispose()

```
override void RCCM.UI.CoordinateSystemSettingsForm.Dispose (
    bool disposing ) [protected]
```

Clean up any resources being used.

Parameters

<i>disposing</i>	true if managed resources should be disposed; otherwise, false.
------------------	---


The documentation for this class was generated from the following files:

- RCCM/UI/CoordinateSystemSettingsForm.cs
- RCCM/UI/CoordinateSystemSettingsForm.Designer.cs

5.7 RCCM.CycleCounter Class Reference

Tracks the cycle number of the test. Can be paused and restarted. This is a virtual implementation of [ICycleCounter](#)

Inheritance diagram for RCCM.CycleCounter:



Public Member Functions

- [CycleCounter](#) (int [period](#))
Create a cycle counter with a fixed period
- void [Start](#) ()
Activates the counter without resetting the cycle number
- void [Start](#) (int cycle)
Activates the counter without and sets the current cycle to the specified value
- void [Stop](#) ()
Stops the cycle counting. Cycle counting can be resumed
- double [GetPressure](#) ()
Get current pressure reading (simulated with sine curve)
Returns
current pressure reading
- int [GetElapsed](#) ()
Elapsed time in test from current cycle and elapsed time since last tick
- async Task [Terminate](#) ()
Implementing a required function that serves no purpose for virtual implementation

Protected Attributes

- Timer [countTimer](#)
Timer for automatically incrementing cycle number
- int [period](#)
Fixed cycle period in milliseconds
- int [lastTick](#)
Environment tick count of last cycle increment

Properties

- bool [Active](#) [get]
A boolean indicating whether or not the counter is active
- int [Cycle](#) [get, set]
Current cycle number
- int [Period](#) [get, set]
Cycle period in milliseconds
- double [Amplitude](#) [get, set]
Amplitude of pressure signal

5.7.1 Detailed Description

Tracks the cycle number of the test. Can be paused and restarted. This is a virtual implementation of [ICycleCounter](#)

5.7.2 Constructor & Destructor Documentation

5.7.2.1 CycleCounter()

```
RCCM.CycleCounter.CycleCounter (
    int period )
```

Create a cycle counter with a fixed period

Parameters

<i>period</i>	Cycle period in milliseconds
---------------	------------------------------

5.7.3 Member Function Documentation

5.7.3.1 GetElapsed()

```
int RCCM.CycleCounter.GetElapsed ( )
```

Elapsed time in test from current cycle and elapsed time since last tick

Implements [RCCM.ICycleCounter](#).

5.7.3.2 GetPressure()

```
double RCCM.CycleCounter.GetPressure ( )
```

Get current pressure reading (simulated with sine curve)

Returns

current pressure reading

Implements [RCCM.ICycleCounter](#).

5.7.3.3 Start() [1/2]

```
void RCCM.CycleCounter.Start ( )
```

Activates the counter without resetting the cycle number

Implements [RCCM.ICycleCounter](#).

5.7.3.4 Start() [2/2]

```
void RCCM.CycleCounter.Start (
    int cycle )
```

Activates the counter without and sets the current cycle to the specified value

Parameters

<i>cycle</i>	Cycle number to start at
--------------	--------------------------

Implements [RCCM.ICycleCounter](#).

5.7.3.5 Stop()

```
void RCCM.CycleCounter.Stop ( )
```

Stops the cycle counting. Cycle counting can be resumed

Implements [RCCM.ICycleCounter](#).

5.7.3.6 Terminate()

```
async Task RCCM.CycleCounter.Terminate ( )
```

Implementing a required function that serves no purpose for virtual implementation

Returns

Nothing

Implements [RCCM.ICycleCounter](#).

5.7.4 Member Data Documentation

5.7.4.1 countTimer

```
Timer RCCM.CycleCounter.countTimer [protected]
```

Timer for automatically incrementing cycle number

5.7.4.2 lastTick

```
int RCCM.CycleCounter.lastTick [protected]
```

Environment tick count of last cycle increment

5.7.4.3 period

```
int RCCM.CycleCounter.period [protected]
```

Fixed cycle period in milliseconds

5.7.5 Property Documentation

5.7.5.1 Active

```
bool RCCM.CycleCounter.Active [get]
```

A boolean indicating whether or not the counter is active

5.7.5.2 Amplitude

```
double RCCM.CycleCounter.Amplitude [get], [set]
```

Amplitude of pressure signal

5.7.5.3 Cycle

```
int RCCM.CycleCounter.Cycle [get], [set]
```

Current cycle number

5.7.5.4 Period

```
int RCCM.CycleCounter.Period [get], [set]
```

Cycle period in milliseconds


The documentation for this class was generated from the following file:

- RCCM/CycleCounter.cs

5.8 RCCM.DataqCycleCounter Class Reference

Cycle counter using analog pressure input to get pressure and cycle

Inheritance diagram for RCCM.DataqCycleCounter:



Public Member Functions

- [DataqCycleCounter](#) ()
Create dataq device and counter. Note: initialization is asynchronous
- void [Start](#) ()
Activates the counter without resetting the cycle number
- void [Start](#) (int cycle)
Activates the counter without and sets the current cycle to the specified value
- void [Stop](#) ()
Stops the cycle counting. Cycle counting can be resumed
- double [GetPressure](#) ()
Get most recent analog pressure reading
- int [GetElapsed](#) ()
Get time elapsed in test in milliseconds
- async Task [Terminate](#) ()
Stop data acquisition and release DATAQ device

Static Public Member Functions

- static double [PwlInterp](#) (double[,] data, double val)
Helper function for piecewise linear interpolation

Static Public Attributes

- static double [THRESHOLD](#) = (double)Program.Settings.json["cycle counter"]["threshold"]
Threshold voltage that must be crossed to interpret as a cycle signal
- static int [IN_PRESSURE](#) = (int)Program.Settings.json["cycle counter"]["pressure input"]
Input channel for pressure reading - a number from 1 to 4
- static int [IN_CYCLE](#) = (int)Program.Settings.json["cycle counter"]["cycle input"]
Input channel for cycle input - a number from 1 to 4

Protected Member Functions

- async void [initialize](#) ()
Asynchronous function that initializes DATAQ device and starts data acquisition
- async void [readDataLoop](#) ()
Worker function for background task that reads data from DATAQ device.

Protected Attributes

- int [elapsed](#)
Accumulator for ticks elapsed in test
- int [startTick](#)
Environment tick count when cycle counting started
- Dataq.Devices.DI1100.Device [di_1100](#)
Handle to DATAQ DI-1100 data acquisition device
- double [,] [calibration](#)
Conversion from volts to pressure. Represented as rows of (voltage, pressure) pairs that are linearly interpolated to get pressure from a given voltage reading
- double [pressure](#)
Stores last pressure reading
- double [lastCycleVoltage](#)
Stores last cycle input reading
- AnalogVoltageIn [pressureChannel](#)
Channel for pressure reading
- AnalogVoltageIn [cycleChannel](#)
Channel for cycle input
- Task [readDataTask](#)
Background task for reading data
- CancellationTokenSource [cancelRead](#)
Token for signalling cancellation to background task

Properties

- bool [Active](#) [get, protected set]
A boolean indicating whether or not the counter is active
- int [Cycle](#) [get, set]
Current cycle number

5.8.1 Detailed Description

Cycle counter using analog pressure input to get pressure and cycle

5.8.2 Constructor & Destructor Documentation

5.8.2.1 DataqCycleCounter()

```
RCCM.DataqCycleCounter.DataqCycleCounter ( )
```

Create dataq device and counter. Note: initialization is asynchronous

5.8.3 Member Function Documentation

5.8.3.1 GetElapsed()

```
int RCCM.DataqCycleCounter.GetElapsed ( )
```

Get time elapsed in test in milliseconds

Returns

Cumulative milliseconds elapsed, accounting for pauses

Implements [RCCM.ICycleCounter](#).

5.8.3.2 GetPressure()

```
double RCCM.DataqCycleCounter.GetPressure ( )
```

Get most recent analog pressure reading

Returns

Last pressure reading recorded

Implements [RCCM.ICycleCounter](#).

5.8.3.3 initialize()

```
async void RCCM.DataqCycleCounter.initialize ( ) [protected]
```

Asynchronous function that initializes DATAQ device and starts data acquisition

5.8.3.4 PwlInterp()

```
static double RCCM.DataqCycleCounter.PwlInterp (
    double data[,],
    double val ) [static]
```

Helper function for piecewise linear interpolation

Parameters

<i>data</i>	2D array of (x, y) value pairs
<i>val</i>	X value to be interpolated

Returns

Interpolated Y value corresponding to input X

5.8.3.5 readDataLoop()

```
async void RCCM.DataqCycleCounter.readDataLoop ( ) [protected]
```

Worker function for background task that reads data from DATAQ device.

5.8.3.6 Start() [1/2]

```
void RCCM.DataqCycleCounter.Start ( )
```

Activates the counter without resetting the cycle number

Implements [RCCM.ICycleCounter](#).

5.8.3.7 Start() [2/2]

```
void RCCM.DataqCycleCounter.Start (
    int cycle )
```

Activates the counter without and sets the current cycle to the specified value

Parameters

<i>cycle</i>	Cycle number to start at
--------------	--------------------------

Implements [RCCM.ICycleCounter](#).

5.8.3.8 Stop()

```
void RCCM.DataqCycleCounter.Stop ( )
```

Stops the cycle counting. Cycle counting can be resumed

Implements [RCCM.ICycleCounter](#).

5.8.3.9 Terminate()

```
async Task RCCM.DataqCycleCounter.Terminate ( )
```

Stop data acquisition and release DATAQ device

Implements [RCCM.ICycleCounter](#).

5.8.4 Member Data Documentation

5.8.4.1 calibration

```
double [,] RCCM.DataqCycleCounter.calibration [protected]
```

Conversion from volts to pressure. Represented as rows of (voltage, pressure) pairs that are linearly interpolated to get pressure from a given voltage reading

5.8.4.2 cancelRead

```
CancellationTokenSource RCCM.DataqCycleCounter.cancelRead [protected]
```

Token for signalling cancellation to background task

5.8.4.3 cycleChannel

```
AnalogVoltageIn RCCM.DataqCycleCounter.cycleChannel [protected]
```

Channel for cycle input

5.8.4.4 di_1100

```
Dataq.Devices.DI1100.Device RCCM.DataqCycleCounter.di_1100 [protected]
```

Handle to DATAQ DI-1100 data acquisition device

5.8.4.5 elapsed

```
int RCCM.DataqCycleCounter.elapsed [protected]
```

Accumulator for ticks elapsed in test

5.8.4.6 IN_CYCLE

```
int RCCM.DataqCycleCounter.IN_CYCLE = (int)Program.Settings.json["cycle counter"]["cycle input"]  
[static]
```

Input channel for cycle input - a number from 1 to 4

5.8.4.7 IN_PRESSURE

```
int RCCM.DataqCycleCounter.IN_PRESSURE = (int)Program.Settings.json["cycle counter"]["pressure  
input"] [static]
```

Input channel for pressure reading - a number from 1 to 4

5.8.4.8 lastCycleVoltage

```
double RCCM.DataqCycleCounter.lastCycleVoltage [protected]
```

Stores last cycle input reading

5.8.4.9 pressure

```
double RCCM.DataqCycleCounter.pressure [protected]
```

Stores last pressure reading

5.8.4.10 pressureChannel

```
AnalogVoltageIn RCCM.DataqCycleCounter.pressureChannel [protected]
```

Channel for pressure reading

5.8.4.11 readDataTask

```
Task RCCM.DataqCycleCounter.readDataTask [protected]
```

Background task for reading data

5.8.4.12 startTick

```
int RCCM.DataqCycleCounter.startTick [protected]
```

Environment tick count when cycle counting started

5.8.4.13 THRESHOLD

```
double RCCM.DataqCycleCounter.THRESHOLD = (double)Program.Settings.json["cycle counter"]["threshold"]  
[static]
```

Threshold voltage that must be crossed to interpret as a cycle signal

5.8.5 Property Documentation

5.8.5.1 Active

```
bool RCCM.DataqCycleCounter.Active [get], [protected set]
```

A boolean indicating whether or not the counter is active

5.8.5.2 Cycle

```
int RCCM.DataqCycleCounter.Cycle [get], [set]
```

Current cycle number


The documentation for this class was generated from the following file:

- RCCM/DataqCycleCounter.cs

5.9 RCCM.ICamera Interface Reference

Interface defining the basic functionalities of the [NFOV](#) and [WFOV](#) cameras to allow both cameras to be referenced by the exact same code

Inheritance diagram for RCCM.ICamera:



Public Member Functions

- void **Start** ()
Begin live image transmission from camera
- void **Stop** ()
Stop live image transmission from camera
- void **Snap** (string filename)
Save live image from camera to bitmap file
- void **Record** (string filename)
Begin recording video from camera
- void **StopRecord** ()
Stop recording video from camera
- bool **CheckFOV** (RCCMSystem rccm)
*Returns true if current state of **RCCM** matches calibration state for FOV*
- void **SetScale** (RCCMSystem rccm, double scale)
Set value for pixel to micron conversion and save relevant info for checking that fov is correct

Properties

- double **Scale** [get]
Conversion from pixels to microns
- double **Height** [get]
Height in microns of image
- double **Width** [get]
Width in microns of image
- bool **Recording** [get]
A flag to indicate if camera is recording video

5.9.1 Detailed Description

Interface defining the basic functionalities of the **NFOV** and **WFOV** cameras to allow both cameras to be referenced by the exact same code

5.9.2 Member Function Documentation

5.9.2.1 CheckFOV()

```
bool RCCM.ICamera.CheckFOV (
    RCCMSystem rccm )
```

Returns true if current state of **RCCM** matches calibration state for FOV

Parameters

<i>rccm</i>	Handle to RCCM object for getting z position
-------------	---

Implemented in [RCCM.NFOV](#), and [RCCM.WFOV](#).

5.9.2.2 Record()

```
void RCCM.ICamera.Record (
    string filename )
```

Begin recording video from camera

Parameters

<i>filename</i>	Path to .avi file where video will save
-----------------	---

Implemented in [RCCM.NFOV](#), and [RCCM.WFOV](#).

5.9.2.3 SetScale()

```
void RCCM.ICamera.SetScale (
    RCCMSystem rccm,
    double scale )
```

Set value for pixel to micron conversion and save relevant info for checking that fov is correct

Parameters

<i>rccm</i>	Handle to RCCM object for getting z position
<i>scale</i>	New value of pixels to microns conversion

Implemented in [RCCM.NFOV](#), and [RCCM.WFOV](#).

5.9.2.4 Snap()

```
void RCCM.ICamera.Snap (
    string filename )
```

Save live image from camera to bitmap file

Parameters

<i>filename</i>	Path to .bmp file where image will save
-----------------	---

Implemented in [RCCM.NFOV](#), and [RCCM.WFOV](#).

5.9.2.5 Start()

```
void RCCM.ICamera.Start ( )
```

Begin live image transmission from camera

Implemented in [RCCM.NFOV](#), and [RCCM.WFOV](#).

5.9.2.6 Stop()

```
void RCCM.ICamera.Stop ( )
```

Stop live image transmission from camera

Implemented in [RCCM.NFOV](#), and [RCCM.WFOV](#).

5.9.2.7 StopRecord()

```
void RCCM.ICamera.StopRecord ( )
```

Stop recording video from camera

Implemented in [RCCM.NFOV](#), and [RCCM.WFOV](#).

5.9.3 Property Documentation

5.9.3.1 Height

```
double RCCM.ICamera.Height [get]
```

Height in microns of image

5.9.3.2 Recording

```
bool RCCM.ICamera.Recording [get]
```

A flag to indicate if camera is recording video

5.9.3.3 Scale

```
double RCCM.ICamera.Scale [get]
```

Conversion from pixels to microns

5.9.3.4 Width

```
double RCCM.ICamera.Width [get]
```


Width in microns of image

The documentation for this interface was generated from the following file:

- RCCM/ICamera.cs

5.10 RCCM.ICycleCounter Interface Reference

Inheritance diagram for RCCM.ICycleCounter:



Public Member Functions

- void [Start](#) ()
Starts cycle counting
- void [Start](#) (int cycle)
Starts cycle counting at the specified cycle number
- void [Stop](#) ()
Stops cycle counting
- double [GetPressure](#) ()
Get most recent pressure reading
- int [GetElapsed](#) ()
Get time elapsed in test
- Task [Terminate](#) ()
Perform any action neccessary for stopping cycle counter

Properties

- bool [Active](#) [get]
A boolean indicating whether or not the counter is active
- int [Cycle](#) [get, set]
Current cycle number

5.10.1 Member Function Documentation

5.10.1.1 GetElapsed()

```
int RCCM.ICycleCounter.GetElapsed ( )
```

Get time elapsed in test

Returns

milliseconds since test start

Implemented in [RCCM.DataqCycleCounter](#), and [RCCM.CycleCounter](#).

5.10.1.2 GetPressure()

```
double RCCM.ICycleCounter.GetPressure ( )
```

Get most recent pressure reading

Returns

Most recent pressure reading

Implemented in [RCCM.DataqCycleCounter](#), and [RCCM.CycleCounter](#).

5.10.1.3 Start() [1/2]

```
void RCCM.ICycleCounter.Start ( )
```

Starts cycle counting

Implemented in [RCCM.DataqCycleCounter](#), and [RCCM.CycleCounter](#).

5.10.1.4 Start() [2/2]

```
void RCCM.ICycleCounter.Start (
    int cycle )
```

Starts cycle counting at the specified cycle number

Implemented in [RCCM.DataqCycleCounter](#), and [RCCM.CycleCounter](#).

5.10.1.5 Stop()

```
void RCCM.ICycleCounter.Stop ( )
```

Stops cycle counting

Implemented in [RCCM.DataqCycleCounter](#), and [RCCM.CycleCounter](#).

5.10.1.6 Terminate()

```
Task RCCM.ICycleCounter.Terminate ( )
```

Perform any action necessary for stopping cycle counter

Returns

Task completion

Implemented in [RCCM.DataqCycleCounter](#), and [RCCM.CycleCounter](#).

5.10.2 Property Documentation

5.10.2.1 Active

```
bool RCCM.ICycleCounter.Active [get]
```

A boolean indicating whether or not the counter is active

5.10.2.2 Cycle

```
int RCCM.ICycleCounter.Cycle [get], [set]
```

Current cycle number


The documentation for this interface was generated from the following file:

- [RCCM/ICycleCounter.cs](#)

5.11 RCCM.IRCCMPlugin Interface Reference

Interface that plugins must implement to provide identifying information about plugin

Inheritance diagram for [RCCM.IRCCMPlugin](#):



Public Member Functions

- [IRCCMPluginActor Instance](#) ([RCCMSystem](#) rccm, Dictionary< string, string > parameters)
Create an instance of the plugin

Properties

- string [Name](#) [get]
User visible name of plugin
- string [] [Params](#) [get]
Plugin inputs

5.11.1 Detailed Description

Interface that plugins must implement to provide identifying information about plugin

5.11.2 Member Function Documentation

5.11.2.1 Instance()

```
IRCCMPluginActor RCCM.IRCCMPlugin.Instance (
    RCCMSystem rccm,
    Dictionary< string, string > parameters )
```

Create an instance of the plugin

Parameters

<i>rccm</i>	Reference to the RCCM object
<i>parameters</i>	User inputs to the plugin

Returns

An instance of the runnable plugin interface

Implemented in [PressureCameraTrigger.PressureCameraTriggerPlugin](#), [CameraCalibration.CameraCalibrationPlugin](#), and [RepeatabilityTest.RepeatabilityTestPlugin](#).

5.11.3 Property Documentation

5.11.3.1 Name

```
string RCCM.IRCCMPlugin.Name [get]
```

User visible name of plugin

5.11.3.2 Params

```
string [] RCCM.IRCCMPlugin.Params [get]
```

Plugin inputs


The documentation for this interface was generated from the following file:

- [RCCM/IRCCMPlugin.cs](#)

5.12 RCCM.IRCCMPluginActor Interface Reference

Interface that allows plugins to define a function that is called to run them

Inheritance diagram for RCCM.IRCCMPluginActor:



Public Member Functions

- void [Run](#) ()
Run the function with the inputs already passed to the plugin
- void [Stop](#) ()
This function should cause the plugin to stop as soon as possible

Properties

- bool [Running](#) [get]
A flag indicating if the plugin is running

5.12.1 Detailed Description

Interface that allows plugins to define a function that is called to run them

5.12.2 Member Function Documentation

5.12.2.1 Run()

```
void RCCM.IRCCMPluginActor.Run ( )
```

Run the function with the inputs already passed to the plugin

Implemented in [CameraCalibration.CameraCalibration](#), [RepeatabilityTest.RepeatabilityTest](#), and [PressureCameraTrigger.PressureCameraTrigger](#).

5.12.2.2 Stop()

```
void RCCM.IRCCMPluginActor.Stop ( )
```

This function should cause the plugin to stop as soon as possible

Implemented in [CameraCalibration.CameraCalibration](#), [RepeatabilityTest.RepeatabilityTest](#), and [PressureCameraTrigger.PressureCameraTrigger](#).

5.12.3 Property Documentation

5.12.3.1 Running

```
bool RCCM.IRCCMPluginActor.Running [get]
```

A flag indicating if the plugin is running


The documentation for this interface was generated from the following file:

- [RCCM/IRCCMPluginActor.cs](#)

5.13 RCCM.UI.LensCalibrationForm Class Reference

GUI for adjusting [NFOV](#) lens focus calibration

Inheritance diagram for RCCM.UI.LensCalibrationForm:



Classes

- class [CalibrationPoint](#)
Value class for storing the input output pairs of a calibration point

Public Member Functions

- [LensCalibrationForm](#) ([RCCMSystem](#) rccm, [RCCMStage](#) stage)
Create a calibration [UI](#) form for the specified stage. Saves changes to specified settings object

Protected Member Functions

- override void [Dispose](#) (bool disposing)
Clean up any resources being used.

Protected Attributes

- [RCCMSystem rccm](#)
The [RCCM](#) object
- [NFOVLensController controller](#)
Lens controller
- [RCCMStage stage](#)
Parent stage of [NFOV](#) camera to be adjusted
- double [,] [oldCalibration](#)
Calibration data before creation of this form. Reverts calibration if cancel is clicked
- SortedList< double, [CalibrationPoint](#) > [calibration](#)
Data of the active calibration that the user is entering

5.13.1 Detailed Description

GUI for adjusting [NFOV](#) lens focus calibration

5.13.2 Constructor & Destructor Documentation

5.13.2.1 LensCalibrationForm()

```
RCCM.UI.LensCalibrationForm.LensCalibrationForm (
    RCCMSystem rccm,
    RCCMStage stage )
```

Create a calibration [UI](#) form for the specified stage. Saves changes to specified settings object

Parameters

<i>controller</i>	NFOV lens controller
<i>stage</i>	Parent stage of NFOV camera to be adjusted

5.13.3 Member Function Documentation

5.13.3.1 Dispose()

```
override void RCCM.UI.LensCalibrationForm.Dispose (
    bool disposing ) [protected]
```

Clean up any resources being used.

Parameters

<i>disposing</i>	true if managed resources should be disposed; otherwise, false.
------------------	---

5.13.4 Member Data Documentation

5.13.4.1 calibration

`SortedList<double, CalibrationPoint> RCCM.UI.LensCalibrationForm.calibration [protected]`

Data of the active calibration that the user is entering

5.13.4.2 controller

`NFOVLensController RCCM.UI.LensCalibrationForm.controller [protected]`

Lens controller

5.13.4.3 oldCalibration

`double [,] RCCM.UI.LensCalibrationForm.oldCalibration [protected]`

Calibration data before creation of this form. Reverts calibration if cancel is clicked

5.13.4.4 rccm

`RCCMSystem RCCM.UI.LensCalibrationForm.rccm [protected]`

The [RCCM](#) object

5.13.4.5 stage

`RCCMStage RCCM.UI.LensCalibrationForm.stage [protected]`

Parent stage of [NFOV](#) camera to be adjusted

The documentation for this class was generated from the following files:

- `RCCM/UI/LensCalibrationForm.cs`
- `RCCM/UI/LensCalibrationForm.Designer.cs`

5.14 RCCM.Logger Class Reference

Helper object for logging debug information with relevant metadata

Static Public Member Functions

- static void `Out` (string *str*, [CallerFilePath] string *path*="", [CallerLineNumber] int *lineNumber*=0, [CallerMemberName] string *caller*="")
Write a line to the logfile
- static void `Save` ()
Save file to disk

Static Public Attributes

- static StreamWriter `Logfile` = new StreamWriter("log/output.txt", false)
Log file where debug info will be saved

5.14.1 Detailed Description

Helper object for logging debug information with relevant metadata

5.14.2 Member Function Documentation

5.14.2.1 Out()

```
static void RCCM.Logger.Out (
    string str,
    [CallerFilePath] string path = "",
    [CallerLineNumber] int lineNumber = 0,
    [CallerMemberName] string caller = "" ) [static]
```

Write a line to the logfile

Parameters

<i>str</i>	Line to write
<i>path</i>	Path of file containing calling function (automatic)
<i>lineNumber</i>	Line number of calling function (automatic)
<i>caller</i>	Calling function (automatic)

5.14.2.2 Save()

```
static void RCCM.Logger.Save ( ) [static]
```

Save file to disk

5.14.3 Member Data Documentation

5.14.3.1 Logfile

```
StreamWriter RCCM.Logger.Logfile = new StreamWriter("log/output.txt", false) [static]
```

Log file where debug info will be saved

The documentation for this class was generated from the following file:

- RCCM/Logger.cs

5.15 RCCM.Measurement Class Reference

Class representing a measurement of a crack vertex and [RCCM](#) data on when it was taken

Public Member Functions

- [Measurement](#) ([MeasurementSequence](#) crack, [RCCMSystem](#) rccm, double pixelX, double pixelY)
Create a measurement
- string [ToCSVString](#) ()
Create csv line containing all data pertaining to this measurement

Static Public Attributes

- static string [] [CSV_HEADER](#) = { "Timestamp", "[Cycle](#)", "Length", "Pressure", "Panel [X](#)", "Panel [Y](#)", "Coarse [X](#)", "Coarse [Y](#)", "Fine [X](#)", "Fine [Y](#)", "Fine [Z](#)", "Height", "Pixel [X](#)", "Pixel [Y](#)", "Global [X](#)", "Global [Y](#)", "Filename" }
Fields for CSV header explaining the ordering of data in measurement file

Properties

- int [Cycle](#) [get]
Cycle number when measurement was taken
- double [X](#) [get]
Global X coordinate where measurement was taken
- double [Y](#) [get]
Global Y coordinate where measurement was taken
- double [PanelX](#) [get]
X coordinate in panel coordinate system
- double [PanelY](#) [get]
Y coordinate in panel coordinate system
- double [CrackLength](#) [get, set]
Length of crack at this measurement
- double **Pressure** [get, protected set]
- string **Timestamp** [get, protected set]
- double **CoarseX** [get, protected set]
- double **CoarseY** [get, protected set]
- double **FineX** [get, protected set]
- double **FineY** [get, protected set]
- double **FineZ** [get, protected set]
- double **Height** [get, protected set]
- double **PixelX** [get, protected set]
- double **PixelY** [get, protected set]
- string **Filename** [get, protected set]

5.15.1 Detailed Description

Class representing a measurement of a crack vertex and [RCCM](#) data on when it was taken

5.15.2 Constructor & Destructor Documentation

5.15.2.1 Measurement()

```
RCCM.Measurement.Measurement (
    MeasurementSequence crack,
    RCCMSystem rccm,
    double pixelX,
    double pixelY )
```

Create a measurement

Parameters

<i>crack</i>	Crack containing this measurement
<i>rccm</i>	Reference to RCCM object
<i>pixelX</i>	Pixel horizontal position within image to measurement
<i>pixelY</i>	Pixel vertical position within image to measurement

5.15.3 Member Function Documentation

5.15.3.1 ToCSVString()

```
string RCCM.Measurement.ToCSVString ( )
```

Create csv line containing all data pertaining to this measurement

Returns

CSV string representing this [Measurement](#)

5.15.4 Member Data Documentation

5.15.4.1 CSV_HEADER

```
string [ ] RCCM.Measurement.CSV_HEADER = { "Timestamp", "Cycle", "Length", "Pressure", "Panel
X", "Panel Y", "Coarse X", "Coarse Y", "Fine X", "Fine Y", "Fine Z", "Height", "Pixel X",
"Pixel Y", "Global X", "Global Y", "Filename" } [static]
```

Fields for CSV header explaining the ordering of data in measurement file

5.15.5 Property Documentation

5.15.5.1 CrackLength

```
double RCCM.Measurement.CrackLength [get], [set]
```

Length of crack at this measurement

5.15.5.2 Cycle

```
int RCCM.Measurement.Cycle [get]
```

Cycle number when measurement was taken

5.15.5.3 PanelX

```
double RCCM.Measurement.PanelX [get]
```

X coordinate in panel coordinate system

5.15.5.4 PanelY

```
double RCCM.Measurement.PanelY [get]
```

Y coordinate in panel coordinate system

5.15.5.5 X

```
double RCCM.Measurement.X [get]
```

Global X coordinate where measurement was taken

5.15.5.6 Y

```
double RCCM.Measurement.Y [get]
```


Global Y coordinate where measurement was taken

The documentation for this class was generated from the following file:

- RCCM/Measurement.cs

5.16 RCCM.MeasurementSequence Class Reference

Inheritance diagram for RCCM.MeasurementSequence:



Public Member Functions

- [MeasurementSequence](#) ([Color](#) color, string name, float size, float orientation, [MeasurementMode](#) mode, string camera)
Create a new measurement sequence with all parameters specified
- [MeasurementSequence](#) ([NewMeasurementForm](#) parentForm)
Create the measurement sequence defined by the NewMeasurementSequence form
- void [AddPoint](#) ([Measurement](#) pt)
Add a point to the list of vertices in this sequence
- [Measurement](#) [GetPoint](#) (int ind)
Get [Measurement](#) corresponding to the specified index
- [Measurement](#) [GetLastPoint](#) ()
Get last [Measurement](#) in sequence
- bool [removePoint](#) (int index)
Deletes a vertex from this sequence
- void [Plot](#) (Graphics axes, float scale)
Plot the line segments of this measurement sequence on a graphics container
- string [GetFileName](#) ()
Create a filename with identifying information about sequence
- bool [WriteToFile](#) (string path, bool autoName)
Write measurement to file. Formatted as one line header followed with a line for each crack vertex
- override string [ToString](#) ()
Return name identifying this sequence
- double [CalculateLength](#) (int ind)
Calculate the length of the crack at the specified measurement
- void [RecomputeLength](#) ()
Recalculate length of crack at time of each measurement

Static Public Attributes

- static int [CrackCount](#) = 0
Counter for number of cracks that have been created so that unique name can be created

Protected Attributes

- List< [Measurement](#) > [points](#)
List of points of crack vertices and relevant metadata
- [MeasurementMode](#) **mode**

Properties

- string **Camera** [get, set]
Indicates which camera captured these measurements
- Color **Color** [get, set]
Color of line to display
- string **Name** [get, set]
Name of sequence for display
- float **LineSize** [get, set]
Width of line
- double **Orientation** [get, set]
Angular orientation (in degrees) of initial notch relative to panel coordinate system
- **MeasurementMode** Mode [get, set]
Method to use for crack length calculation
- int **CountPoints** [get]
Number of points in sequence
- string **CreateTime** [get]
- string **SaveDir** [get]

5.16.1 Constructor & Destructor Documentation

5.16.1.1 MeasurementSequence() [1/2]

```
RCCM.MeasurementSequence.MeasurementSequence (
    Color color,
    string name,
    float size,
    float orientation,
    MeasurementMode mode,
    string camera )
```

Create a new measurement sequence with all parameters specified

Parameters

<i>color</i>	Color of line representation on NFOV image
<i>name</i>	Name identifying crack
<i>size</i>	Thickness of line on NFOV image
<i>orientation</i>	Angular orientation (degrees) of initial crack notch
<i>mode</i>	Crack length calculation method
<i>camera</i>	Camera used to image crack

5.16.1.2 MeasurementSequence() [2/2]

```
RCCM.MeasurementSequence.MeasurementSequence (
    NewMeasurementForm parentForm )
```

Create the measurement sequence defined by the NewMeasurementSequence form

Parameters

<i>parentForm</i>	
-------------------	--

5.16.2 Member Function Documentation

5.16.2.1 AddPoint()

```
void RCCM.MeasurementSequence.AddPoint (
    Measurement pt )
```

Add a point to the list of vertices in this sequence

Parameters

<i>pt</i>	Crack vertex
-----------	--------------

5.16.2.2 CalculateLength()

```
double RCCM.MeasurementSequence.CalculateLength (
    int ind )
```

Calculate the length of the crack at the specified measurement

Parameters

<i>ind</i>	Index in measurement sequence of the desired measurement
------------	--

Returns

Crack length when specified measurement was made

5.16.2.3 GetFileName()

```
string RCCM.MeasurementSequence.GetFileName ( )
```

Create a filename with identifying information about sequence

Returns

Filename formatted with current timestamp, crack name, and .csv extension

5.16.2.4 GetLastPoint()

```
Measurement RCCM.MeasurementSequence.GetLastPoint ( )
```

Get last [Measurement](#) in sequence

Returns

[Measurement](#) at last index

5.16.2.5 GetPoint()

```
Measurement RCCM.MeasurementSequence.GetPoint (
    int ind )
```

Get [Measurement](#) corresponding to the specified index

Parameters

<i>ind</i>	Index of measurement to return
------------	--------------------------------

Returns

[Measurement](#) at this index if it is valid

5.16.2.6 Plot()

```
void RCCM.MeasurementSequence.Plot (
    Graphics axes,
    float scale )
```

Plot the line segments of this measurement sequence on a graphics container

Parameters

<i>axes</i>	Graphics object of the container that will display the plot
-------------	---

5.16.2.7 RecomputeLength()

```
void RCCM.MeasurementSequence.RecomputeLength ( )
```

Recalculate length of crack at time of each measurement

5.16.2.8 removePoint()

```
bool RCCM.MeasurementSequence.removePoint (
    int index )
```

Deletes a vertex from this sequence

Parameters

<i>index</i>	Index of the vertex to be deleted
--------------	-----------------------------------

Returns

True or false if deletion was successful

5.16.2.9 ToString()

```
override string RCCM.MeasurementSequence.ToString ( )
```

Return name identifying this sequence

Returns

Sequence name

5.16.2.10 WriteToFile()

```
bool RCCM.MeasurementSequence.WriteToFile (
    string path,
    bool autoName )
```

Write measurement to file. Formatted as one line header followed with a line for each crack vertex

Parameters

<i>path</i>	Filename and directory path where data will be saved
<i>autoName</i>	If true, filename will be automatically defined

Returns

T/F if the write was / wasn't successful

5.16.3 Member Data Documentation

5.16.3.1 CrackCount

```
int RCCM.MeasurementSequence.CrackCount = 0 [static]
```

Counter for number of cracks that have been created so that unique name can be created

5.16.3.2 points

```
List<Measurement> RCCM.MeasurementSequence.points [protected]
```

List of points of crack vertices and relevant metadata

5.16.4 Property Documentation

5.16.4.1 Camera

```
string RCCM.MeasurementSequence.Camera [get], [set]
```

Indicates which camera captured these measurements

5.16.4.2 Color

```
Color RCCM.MeasurementSequence.Color [get], [set]
```

Color of line to display

5.16.4.3 CountPoints

```
int RCCM.MeasurementSequence.CountPoints [get]
```

Number of points in sequence

5.16.4.4 LineSize

```
float RCCM.MeasurementSequence.LineSize [get], [set]
```

Width of line

5.16.4.5 Mode

`MeasurementMode` `RCCM.MeasurementSequence.Mode` `[get]`, `[set]`

Method to use for crack length calculation

5.16.4.6 Name

`string` `RCCM.MeasurementSequence.Name` `[get]`, `[set]`

Name of sequence for display

5.16.4.7 Orientation

`double` `RCCM.MeasurementSequence.Orientation` `[get]`, `[set]`

Angular orientation (in degrees) of initial notch relative to panel coordinate system


The documentation for this class was generated from the following file:

- `RCCM/MeasurementSequence.cs`

5.17 RCCM.Motor Class Reference

Abstract representation of stepper motor. Defines the minimum functions and variables needed to define the motor

Inheritance diagram for `RCCM.Motor`:



Public Member Functions

- [Motor](#) ()
Initialize variables associated with base motor class
- abstract double [GetPos](#) ()
Get current position of actuator
- abstract double [SetPos](#) (double cmd)
Set new command position of actuator
- abstract double [MoveRel](#) (double dist)
Move actuator specified distance from current position
- virtual bool [SetProperty](#) (string property, double value)
Set a motor property
- virtual double [GetProperty](#) (string property)
Gets a motor property value
- void [GotoHome](#) ()
Move to user defined home position
- abstract bool [Initialize](#) ()
Perform any required initialization
- abstract Dictionary< string, double > [GetAllProperties](#) ()
Get all motor settings in a property value pair dictionary
- abstract void [WaitForEndOfMove](#) ()
Blocking function that runs until current actuator move completes
- abstract void [Jog](#) (bool fwd)
Begin continuously moving actuator at jog speed
- abstract void [JogStop](#) ()
Stop jogging
- virtual double [GetActuatorPos](#) ()
Must return actual position of actuator from end of travel. Important for Z actuators
- virtual void [Zero](#) ()
Define current actuator position as zero
- virtual void [Terminate](#) ()
Perform any required action to disconnect from motor

Static Public Attributes

- static string [] [MOTOR_SETTINGS](#) = { "enabled", "microstep per mm", "velocity", "jog speed", "acceleration", "deceleration", "low position limit", "high position limit", "home", "feedback" }
List of motor setting names that all motor implementations must include

Protected Attributes

- double [commandPos](#) = 0
Current goal position of actuator
- Dictionary< string, double > [settings](#)
Maintained list of motion settings and limits

Properties

- bool [Jogging](#) [get, protected set]
A flag to indicate if the motor is being jogged

5.17.1 Detailed Description

Abstract representation of stepper motor. Defines the minimum functions and variables needed to define the motor

5.17.2 Constructor & Destructor Documentation

5.17.2.1 Motor()

```
RCCM.Motor.Motor ( )
```

Initialize variables associated with base motor class

5.17.3 Member Function Documentation

5.17.3.1 GetActuatorPos()

```
virtual double RCCM.Motor.GetActuatorPos ( ) [virtual]
```

Must return actual position of actuator from end of travel. Important for Z actuators

Returns

Position of actuator from end of travel

Reimplemented in [RCCM.TrioStepperZMotor](#).

5.17.3.2 GetAllProperties()

```
abstract Dictionary<string, double> RCCM.Motor.GetAllProperties ( ) [pure virtual]
```

Get all motor settings in a property value pair dictionary

Returns

Dictionary of properties and values

Implemented in [RCCM.TrioStepperZMotor](#), [RCCM.TrioStepperMotor](#), and [RCCM.VirtualMotor](#).

5.17.3.3 GetPos()

```
abstract double RCCM.Motor.GetPos ( ) [pure virtual]
```

Get current position of actuator

Returns

Current position of actuator

Implemented in [RCCM.TrioStepperZMotor](#), [RCCM.TrioStepperMotor](#), and [RCCM.VirtualMotor](#).

5.17.3.4 GetProperty()

```
virtual double RCCM.Motor.GetProperty (
    string property ) [virtual]
```

Gets a motor property value

Parameters

<i>property</i>	Name of the property
-----------------	----------------------

Returns

The value of the specified property

Reimplemented in [RCCM.TrioStepperZMotor](#), and [RCCM.TrioStepperMotor](#).

5.17.3.5 GotoHome()

```
void RCCM.Motor.GotoHome ( )
```

Move to user defined home position

5.17.3.6 Initialize()

```
abstract bool RCCM.Motor.Initialize ( ) [pure virtual]
```

Perform any required initialization

Returns

True if initialization was successful

Implemented in [RCCM.TrioStepperZMotor](#), [RCCM.TrioStepperMotor](#), and [RCCM.VirtualMotor](#).

5.17.3.7 Jog()

```
abstract void RCCM.Motor.Jog (
    bool fwd ) [pure virtual]
```

Begin continuously moving actuator at jog speed

Parameters

<i>fwd</i>	Direction of jog - forward if true
------------	------------------------------------

Implemented in [RCCM.TrioStepperZMotor](#), [RCCM.VirtualMotor](#), and [RCCM.TrioStepperMotor](#).

5.17.3.8 JogStop()

```
abstract void RCCM.Motor.JogStop ( ) [pure virtual]
```

Stop jogging

Implemented in [RCCM.TrioStepperZMotor](#), [RCCM.VirtualMotor](#), and [RCCM.TrioStepperMotor](#).

5.17.3.9 MoveRel()

```
abstract double RCCM.Motor.MoveRel (
    double dist ) [pure virtual]
```

Move actuator specified distance from current position

Parameters

<i>dist</i>	Distance to move
-------------	------------------

Returns

Previous commanded position

Implemented in [RCCM.TrioStepperZMotor](#), [RCCM.TrioStepperMotor](#), and [RCCM.VirtualMotor](#).

5.17.3.10 SetPos()

```
abstract double RCCM.Motor.SetPos (
    double cmd ) [pure virtual]
```

Set new command position of actuator

Parameters

<i>cmd</i>	New goal position to send to actuator
------------	---------------------------------------

Returns

Goal position that was set, coerced if input was out of travel range

Implemented in [RCCM.TrioStepperZMotor](#), [RCCM.TrioStepperMotor](#), and [RCCM.VirtualMotor](#).

5.17.3.11 SetProperty()

```
virtual bool RCCM.Motor.SetProperty (  
    string property,  
    double value ) [virtual]
```

Set a motor property

Parameters

<i>property</i>	Property name
<i>value</i>	Property value

Returns

True if property set is successful

Reimplemented in [RCCM.TrioStepperZMotor](#), and [RCCM.TrioStepperMotor](#).

5.17.3.12 Terminate()

```
virtual void RCCM.Motor.Terminate ( ) [virtual]
```

Perform any required action to disconnect from motor

Reimplemented in [RCCM.TrioStepperZMotor](#).

5.17.3.13 WaitForEndOfMove()

```
abstract void RCCM.Motor.WaitForEndOfMove ( ) [pure virtual]
```

Blocking function that runs until current actuator move completes

Implemented in [RCCM.TrioStepperZMotor](#), [RCCM.TrioStepperMotor](#), and [RCCM.VirtualMotor](#).

5.17.3.14 Zero()

```
virtual void RCCM.Motor.Zero ( ) [virtual]
```

Define current actuator position as zero

Reimplemented in [RCCM.TrioStepperZMotor](#), and [RCCM.TrioStepperMotor](#).

5.17.4 Member Data Documentation

5.17.4.1 commandPos

```
double RCCM.Motor.commandPos = 0 [protected]
```

Current goal position of actuator

5.17.4.2 MOTOR_SETTINGS

```
string [] RCCM.Motor.MOTOR_SETTINGS = { "enabled", "microstep per mm", "velocity", "jog speed",
"acceleration", "deceleration", "low position limit", "high position limit", "home", "feedback"
} [static]
```

List of motor setting names that all motor implementations must include

5.17.4.3 settings

```
Dictionary<string, double> RCCM.Motor.settings [protected]
```

Maintained list of motion settings and limits

5.17.5 Property Documentation

5.17.5.1 Jogging

```
bool RCCM.Motor.Jogging [get], [protected set]
```

A flag to indicate if the motor is being jogged


The documentation for this class was generated from the following file:

- RCCM/Motor.cs

5.18 RCCM.UI.MotorSettingsForm Class Reference

Form for adjusting settings of individual actuators

Inheritance diagram for RCCM.UI.MotorSettingsForm:



Public Member Functions

- [MotorSettingsForm](#) ([RCCMSystem](#) rccm)
Create form

Protected Member Functions

- override void [Dispose](#) (bool disposing)
Clean up any resources being used.

Protected Attributes

- readonly [RCCMSystem](#) **rccm**

5.18.1 Detailed Description

Form for adjusting settings of individual actuators

5.18.2 Constructor & Destructor Documentation

5.18.2.1 MotorSettingsForm()

```
RCCM.UI.MotorSettingsForm.MotorSettingsForm (  
    RCCMSystem rccm )
```

Create form

Parameters

<i>rccm</i>	Reference to RCCM object
-------------	--

5.18.3 Member Function Documentation

5.18.3.1 Dispose()

```
override void RCCM.UI.MotorSettingsForm.Dispose (  
    bool disposing ) [protected]
```

Clean up any resources being used.

Parameters

<i>disposing</i>	true if managed resources should be disposed; otherwise, false.
------------------	---


The documentation for this class was generated from the following files:

- RCCM/UI/MotorSettingsForm.cs
- RCCM/UI/MotorSettingsForm.Designer.cs

5.19 RCCM.UI.NewMeasurementForm Class Reference

Form for defining settings for a new [MeasurementSequence](#)

Inheritance diagram for RCCM.UI.NewMeasurementForm:



Public Member Functions

- [NewMeasurementForm](#) (string defaultName, string camera)
Open a measurement creation form for the specified camera
- [NewMeasurementForm](#) ([MeasurementSequence](#) crack)
Open a form to edit the given crack
- string [GetName](#) ()
Get name defined on form
- Color [GetColor](#) ()
Get color selected with color picker dialog on form
- float [GetLineSize](#) ()
Get line size defined on form
- double [GetOrientation](#) ()
Get crack orientation defined on form
- [MeasurementMode](#) [GetMode](#) ()
Get selected measurement mode from form
- string [GetCamera](#) ()
Get name of camera capturing this crack

Static Public Attributes

- static int **ColorInd** = 0
- static Color [] **Colors** = { Color.Red, Color.Blue, Color.Green, Color.Purple, Color.Orange, Color.Yellow, Color.Black, Color.Brown, Color.DarkBlue, Color.LimeGreen, Color.PaleVioletRed }

Protected Member Functions

- override void [Dispose](#) (bool disposing)
Clean up any resources being used.

Protected Attributes

- string **camera**

5.19.1 Detailed Description

Form for defining settings for a new [MeasurementSequence](#)

5.19.2 Constructor & Destructor Documentation

5.19.2.1 NewMeasurementForm() [1/2]

```
RCCM.UI.NewMeasurementForm.NewMeasurementForm (
    string defaultName,
    string camera )
```

Open a measurement creation form for the specified camera

Parameters

<i>defaultName</i>	Name to show in name field
<i>camera</i>	Name of camera capturing this measurement

5.19.2.2 NewMeasurementForm() [2/2]

```
RCCM.UI.NewMeasurementForm.NewMeasurementForm (
    MeasurementSequence crack )
```

Open a form to edit the given crack

Parameters

<i>crack</i>	Crack to be edited
--------------	--------------------

5.19.3 Member Function Documentation

5.19.3.1 Dispose()

```
override void RCCM.UI.NewMeasurementForm.Dispose (
    bool disposing ) [protected]
```

Clean up any resources being used.

Parameters

<i>disposing</i>	true if managed resources should be disposed; otherwise, false.
------------------	---

5.19.3.2 GetCamera()

```
string RCCM.UI.NewMeasurementForm.GetCamera ( )
```

Get name of camera capturing this crack

Returns

The name of the camera capturing this [MeasurementSequence](#)

5.19.3.3 GetColor()

```
Color RCCM.UI.NewMeasurementForm.GetColor ( )
```

Get color selected with color picker dialog on form

Returns

The selected color

5.19.3.4 GetLineSize()

```
float RCCM.UI.NewMeasurementForm.GetLineSize ( )
```

Get line size defined on form

Returns

The given line size for the [MeasurementSequence](#)

5.19.3.5 GetMode()

```
MeasurementMode RCCM.UI.NewMeasurementForm.GetMode ( )
```

Get selected measurement mode from form

Returns

The enum value for the selected measurement mode

5.19.3.6 GetName()

```
string RCCM.UI.NewMeasurementForm.GetName ( )
```

Get name defined on form

Returns

The given name for the [MeasurementSequence](#)

5.19.3.7 GetOrientation()

```
double RCCM.UI.NewMeasurementForm.GetOrientation ( )
```

Get crack orientation defined on form

Returns

Orientation angle of crack


The documentation for this class was generated from the following files:

- RCCM/UI/NewMeasurementForm.cs
- RCCM/UI/NewMeasurementForm.Designer.cs

5.20 RCCM.NFOV Class Reference

Class that handles connecting to and operating [NFOV](#) camera (BlackFly

Inheritance diagram for RCCM.NFOV:



Public Member Functions

- [NFOV](#) (string name)
Create a [NFOV](#) camera from its serial number and apply the specified calibration
- bool [Initialize](#) ()
Attempt to connect to camera
- void [Disconnect](#) ()
Stop live capture and release camera
- void [Start](#) ()
Start live streaming images from camera
- void [Stop](#) ()
Stop live streaming images
- void [ShowPropertiesDlg](#) ()
Open dialog box for setting camera properties
- void [Snap](#) (string filename)
Save live image to file
- void [Record](#) (string aviFileName)
Begins recording by signalling to grab loop start of recording
- void [StopRecord](#) ()
Stops recording by indicating to grab loop that recording is done
- void [SetScale](#) ([RCCMSystem](#) rccm, double scale)
Set image scale and save current height
- bool [CheckFOV](#) ([RCCMSystem](#) rccm)
Check if measurement conditions match calibration conditions
- System.Drawing.Bitmap [GetLiveImage](#) ()
Return current live image

Static Public Attributes

- static uint **PACKET_SIZE** = 4000
Bytes to send in a single packet. Configured for jumbo packets
- static uint **PACKET_DELAY** = 6000
Added delay between packets to prevent dropped frames
- static uint **CHANNEL** = 0
Added delay between packets to prevent dropped frames

Protected Attributes

- uint **pixelHeight**
- uint **pixelWidth**
- uint **serial**
Serial number of camera
- ManagedGigECamera **camera**
Camera object
- ManagedImage **rawImage**
Binary image from camera buffer
- bool **grabImages**
Flag to direct grab thread to get the live image
- AutoResetEvent **grabThreadExited**
- BackgroundWorker **grabThread**
Background worker for grabbing images from camera
- string **videoFileName**
Filename that currently recording video will save to

Properties

- uint **PixelHeight** [get, set]
Height in pixels of image
- uint **PixelWidth** [get, set]
Width in pixels of image
- ManagedImage **ProcessedImage** [get]
Converted image
- bool **Connected** [get, protected set]
Indicates if camera is connected
- double **Scale** [get, protected set]
Camera microns / pixel calibration
- double **Height** [get]
Height in mm of image
- double **Width** [get]
Height in mm of image
- bool **Recording** [get, set]
Flag indicating if camera is recording video
- double **CalibrationHeight** [get, protected set]
Height at which calibration was made

5.20.1 Detailed Description

Class that handles connecting to and operating [NFOV](#) camera (BlackFly

5.20.2 Constructor & Destructor Documentation

5.20.2.1 NFOV()

```
RCCM.NFOV.NFOV (
    string name )
```

Create a [NFOV](#) camera from its serial number and apply the specified calibration

Parameters

<i>name</i>	Name of camera in settings
-------------	----------------------------

5.20.3 Member Function Documentation

5.20.3.1 CheckFOV()

```
bool RCCM.NFOV.CheckFOV (
    RCCMSystem rccm )
```

Check if measurement conditions match calibration conditions

Parameters

<i>rccm</i>	
-------------	--

Returns

True if measurement conditions match calibration

Implements [RCCM.ICamera](#).

5.20.3.2 Disconnect()

```
void RCCM.NFOV.Disconnect ( )
```

Stop live capture and release camera

5.20.3.3 GetLiveImage()

```
System.Drawing.Bitmap RCCM.NFOV.GetLiveImage ( )
```

Return current live image

Returns

Live image as a bitmap

5.20.3.4 Initialize()

```
bool RCCM.NFOV.Initialize ( )
```

Attempt to connect to camera

Returns

True if connection is successful

5.20.3.5 Record()

```
void RCCM.NFOV.Record (
    string aviFileName )
```

Begins recording by signalling to grab loop start of recording

Parameters

<i>aviFileName</i>	Path to .avi file where video will save
--------------------	---

Implements [RCCM.ICamera](#).

5.20.3.6 SetScale()

```
void RCCM.NFOV.SetScale (
    RCCMSystem rccm,
    double scale )
```

Set image scale and save current height

Parameters

<i>rccm</i>	
<i>scale</i>	New calibration

Implements [RCCM.ICamera](#).

5.20.3.7 ShowPropertiesDlg()

```
void RCCM.NFOV.ShowPropertiesDlg ( )
```

Open dialog box for setting camera properties

5.20.3.8 Snap()

```
void RCCM.NFOV.Snap (
    string filename )
```

Save live image to file

Parameters

<i>filename</i>	Full path where image will be saved
-----------------	-------------------------------------

Implements [RCCM.ICamera](#).

5.20.3.9 Start()

```
void RCCM.NFOV.Start ( )
```

Start live streaming images from camera

Implements [RCCM.ICamera](#).

5.20.3.10 Stop()

```
void RCCM.NFOV.Stop ( )
```

Stop live streaming images

Implements [RCCM.ICamera](#).

5.20.3.11 StopRecord()

```
void RCCM.NFOV.StopRecord ( )
```

Stops recording by indicating to grab loop that recording is done

Implements [RCCM.ICamera](#).

5.20.4 Member Data Documentation

5.20.4.1 camera

```
ManagedGigECamera RCCM.NFOV.camera [protected]
```

Camera object

5.20.4.2 CHANNEL

```
uint RCCM.NFOV.CHANNEL = 0 [static]
```

Added delay between packets to prevent dropped frames

5.20.4.3 grabImages

```
bool RCCM.NFOV.grabImages [protected]
```

Flag to direct grab thread to get the live image

5.20.4.4 grabThread

```
BackgroundWorker RCCM.NFOV.grabThread [protected]
```

Background worker for grabbing images from camera

5.20.4.5 grabThreadExited

```
AutoResetEvent RCCM.NFOV.grabThreadExited [protected]
```

5.20.4.6 PACKET_DELAY

```
uint RCCM.NFOV.PACKET_DELAY = 6000 [static]
```

Added delay between packets to prevent dropped frames

5.20.4.7 PACKET_SIZE

```
uint RCCM.NFOV.PACKET_SIZE = 4000 [static]
```

Bytes to send in a single packet. Configured for jumbo packets

5.20.4.8 rawImage

```
ManagedImage RCCM.NFOV.rawImage [protected]
```

Binary image from camera buffer

5.20.4.9 serial

```
uint RCCM.NFOV.serial [protected]
```

Serial number of camera

5.20.4.10 videoFileName

```
string RCCM.NFOV.videoFileName [protected]
```

Filename that currently recording video will save to

5.20.5 Property Documentation

5.20.5.1 CalibrationHeight

```
double RCCM.NFOV.CalibrationHeight [get], [protected set]
```

Height at which calibration was made

5.20.5.2 Connected

```
bool RCCM.NFOV.Connected [get], [protected set]
```

Indicates if camera is connected

5.20.5.3 Height

```
double RCCM.NFOV.Height [get]
```

Height in mm of image

5.20.5.4 PixelHeight

```
uint RCCM.NFOV.PixelHeight [get], [set]
```

Height in pixels of image

5.20.5.5 PixelWidth

```
uint RCCM.NFOV.PixelWidth [get], [set]
```

Width in pixels of image

5.20.5.6 ProcessedImage

```
ManagedImage RCCM.NFOV.ProcessedImage [get]
```

Converted image

5.20.5.7 Recording

```
bool RCCM.NFOV.Recording [get], [set]
```

Flag indicating if camera is recording video

5.20.5.8 Scale

```
double RCCM.NFOV.Scale [get], [protected set]
```

Camera microns / pixel calibration

5.20.5.9 Width

```
double RCCM.NFOV.Width [get]
```

Height in mm of image

The documentation for this class was generated from the following file:

- `RCCM/NFOV.cs`

5.21 RCCM.NFOVLensController Class Reference

Class for operating Gardasoft controller and focusing both optotune liquid lenses

Public Member Functions

- [NFOVLensController](#) (int nfov1Serial, int nfov2Serial, double[] [conversion1](#), double[] [conversion2](#), double[,] calibration1, double[,] calibration2)
Initialize autofocusing of [NFOV](#) lens controllers
- double [GetReading](#) ([RCCMStage](#) stage)
Get current input voltage to distanc sensor of specified [NFOV](#)
- double [GetHeight](#) ([RCCMStage](#) stage)
Get current height of specified [NFOV](#)
- double [GetFocalPower](#) ([RCCMStage](#) stage)
Get current focal power of specified [NFOV](#) lens
- bool [ApplyCalibration](#) (double[,] data, [RCCMStage](#) stage)
Applies a calibration to the lens. This scales the focal power based off the distance sensor reading according to a piecewise linear interpolant
- bool [SetFocalPower](#) (double power, [RCCMStage](#) stage)
Sends command to specified controller to set a constant focal power value
- double [ToHeight1](#) (double inputVoltage)
Convert input voltage to distance for [NFOV](#) 1
- double [ToHeight2](#) (double inputVoltage)
Convert input voltage to distance for [NFOV](#) 2
- void [PauseFocusing](#) ([RCCMStage](#) stage)
Pause autofocus loop for specified stage
- void [ResumeFocusing](#) ([RCCMStage](#) stage)
Unpause autofocus loop for specified stage
- void [Save](#) ()
Save calibrations to settings
- void [Stop](#) ()
Stops the focusing thread. Should be called when exiting program

Static Public Member Functions

- static double [PwlInterp](#) (double[,] data, double val)
Helper function for interpolating calibration

Static Public Attributes

- static string [GET_VOLTAGE_CMD](#) = "AN3"
Gardasoft command string for getting current input voltage
- static string [GET_STATUS_CMD](#) = "ST"
Gardasoft command string for getting current status (including output focal power)
- static string [SET_FOCALPOWER_CMD](#) = "RS1"
Gardasoft command string for setting output focal power
- static Regex [PARSE_GET](#) = new Regex(@"lg([0-9]+)")
Regex for parsing get status command response for input voltage
- static Regex [PARSE_GETOUTPUT](#) = new Regex(@"AF\s+([0-9.-]+)")

- Regex for parsing status command for output focal power*
- static long `UPDATE_PERIOD` = (long)Program.Settings.json["distance sensor"]["focus update period"]
Setting for period between focal power updates
- static double `MIN_HEIGHT` = (double)Program.Settings.json["distance sensor"]["min height"]
Minimum height value to send when reading is out of range
- static double `MAX_HEIGHT` = (double)Program.Settings.json["distance sensor"]["max height"]
Maximum height value to send when reading is out of range
- static double `alpha` = (double)Program.Settings.json["distance sensor"]["height reading filter constant"]
Exponential moving average filter constant applied to distance reading

Protected Attributes

- ControllerManager `manager`
Gardasoft controller manager for detecting lens controllers
- bool `read`
Flag to indicate if input power should be read
- bool `readThread1Paused`
Flag to indicate to background thread if it should autofocus [NFOV 1](#)
- bool `readThread2Paused`
Flag to indicate to background thread if it should autofocus [NFOV 2](#)
- BackgroundWorker `bw1`
Background worker for focusing [NFOV 1](#)
- BackgroundWorker `bw2`
Background worker for focusing [NFOV 2](#)
- AutoResetEvent `readHeight1ThreadExited`
Event handler for when [NFOV 1](#) background thread exits
- AutoResetEvent `readHeight2ThreadExited`
Event handler for when [NFOV 2](#) background thread exits

Properties

- IController `NFOV1Controller` [get]
Controller interface for [NFOV 1](#)
- IController `NFOV2Controller` [get]
Controller interface for [NFOV 2](#)
- double `FocusOffset1` [get, set]
Adjustment offset to add to output focal power for [NFOV 1](#)
- double `FocusOffset2` [get, set]
Adjustment offset to add to output focal power for [NFOV 2](#)
- double [] `conversion1` [get]
Slope, y-intercept of conversion from input voltage to distance ([NFOV 1](#))
- double [] `conversion2` [get]
Slope, y-intercept of conversion from input voltage to distance ([NFOV 2](#))
- double [,] `NFOV1Calibration` [get]
Array of input voltage, output focal power pairs to interpolate for [NFOV 1](#)
- double [,] `NFOV2Calibration` [get]
Array of input voltage, output focal power pairs to interpolate for [NFOV 2](#)
- double `Height1` [get]
Current height reading for [NFOV 1](#)
- double `Height2` [get]

- Current height reading for [NFOV 2](#)*
 - [TrioStepperZMotor Motor1](#) [get, set]
- Z motor for [NFOV 1](#)*
 - [TrioStepperZMotor Motor2](#) [get, set]
- Z motor for [NFOV 2](#)*

5.21.1 Detailed Description

Class for operating Gardasoft controller and focusing both optotune liquid lenses

5.21.2 Constructor & Destructor Documentation

5.21.2.1 NFOVLensController()

```
RCCM.NFOVLensController.NFOVLensController (
    int nfov1Serial,
    int nfov2Serial,
    double [ ] conversion1,
    double [ ] conversion2,
    double calibration1[,],
    double calibration2[,] )
```

Initialize autofocusing of [NFOV](#) lens controllers

Parameters

<i>nfov1Serial</i>	Serial number of NFOV 1 gardasoft controller
<i>nfov2Serial</i>	Serial number of NFOV 2 gardasoft controller
<i>conversion1</i>	Conversion loaded from settings for NFOV 1
<i>conversion2</i>	Conversion loaded from settings for NFOV 2
<i>calibration1</i>	Lens calibration loaded from settings for NFOV 1
<i>calibration2</i>	Lens calibration loaded from settings for NFOV 2

5.21.3 Member Function Documentation

5.21.3.1 ApplyCalibration()

```
bool RCCM.NFOVLensController.ApplyCalibration (
    double data[,],
    RCCMStage stage )
```

Applies a calibration to the lens. This scales the focal power based off the distance sensor reading according to a piecewise linear interpolant

Parameters

<i>data</i>	2D array of calibration data. Column 1 contains input voltage, column 2 contains output voltage
<i>stage</i>	Parent stage of the lens to indicate which lens to calibrate

Returns

True if calibration was valid

5.21.3.2 GetFocalPower()

```
double RCCM.NFOVLensController.GetFocalPower (
    RCCMStage stage )
```

Get current focal power of specified **NFOV** lens

Parameters

<i>stage</i>	Enum value of desired lens
--------------	----------------------------

Returns

Current focal power output

5.21.3.3 GetHeight()

```
double RCCM.NFOVLensController.GetHeight (
    RCCMStage stage )
```

Get current height of specified **NFOV**

Parameters

<i>stage</i>	Enum value of desired stage
--------------	-----------------------------

Returns

Current focal height in user units

5.21.3.4 GetReading()

```
double RCCM.NFOVLensController.GetReading (
    RCCMStage stage )
```

Get current input voltage to distanc sensor of specified **NFOV**

Parameters

<i>stage</i>	Enum value of desired lens
--------------	----------------------------

Returns

Current input voltage

5.21.3.5 PauseFocusing()

```
void RCCM.NFOVLensController.PauseFocusing (
    RCCMStage stage )
```

Pause autofocus loop for specified stage

Parameters

<i>stage</i>	Enum value corresponding to desired stage
--------------	---

5.21.3.6 PwInterp()

```
static double RCCM.NFOVLensController.PwInterp (
    double data[,],
    double val ) [static]
```

Helper function for interpolating calibration

Parameters

<i>data</i>	Array of x, y pairs
<i>val</i>	X value to be interpolated

Returns

Interpolated Y value

5.21.3.7 ResumeFocusing()

```
void RCCM.NFOVLensController.ResumeFocusing (
    RCCMStage stage )
```

Unpause autofocus loop for specified stage

Parameters

<i>stage</i>	Enum value corresponding to desired stage
--------------	---

5.21.3.8 Save()

```
void RCCM.NFOVLensController.Save ( )
```

Save calibrations to settings

5.21.3.9 SetFocalPower()

```
bool RCCM.NFOVLensController.SetFocalPower (
    double power,
    RCCMStage stage )
```

Sends command to specified controller to set a constant focal power value

Parameters

<i>power</i>	Focal power to use, in diopters
<i>stage</i>	Stage indicating which controller to send the command to

Returns

True if command succeeded

5.21.3.10 Stop()

```
void RCCM.NFOVLensController.Stop ( )
```

Stops the focusing thread. Should be called when exiting program

5.21.3.11 ToHeight1()

```
double RCCM.NFOVLensController.ToHeight1 (
    double inputVoltage )
```

Convert input voltage to distance for [NFOV 1](#)

Parameters

<i>inputVoltage</i>	Input voltage from distance sensor on NFOV 1
---------------------	--

Returns

Height corresponding to input

5.21.3.12 ToHeight2()

```
double RCCM.NFOVLensController.ToHeight2 (
    double inputVoltage )
```

Convert input voltage to distance for [NFOV 2](#)

Parameters

<i>inputVoltage</i>	Input voltage from distance sensor on NFOV 2
---------------------	--

Returns

Height corresponding to input

5.21.4 Member Data Documentation**5.21.4.1 alpha**

```
double RCCM.NFOVLensController.alpha = (double)Program.Settings.json["distance sensor"]["height
reading filter constant"] [static]
```

Exponential moving average filter constant applied to distance reading

5.21.4.2 bw1

```
BackgroundWorker RCCM.NFOVLensController.bw1 [protected]
```

Background worker for focusing [NFOV 1](#)

5.21.4.3 bw2

```
BackgroundWorker RCCM.NFOVLensController.bw2 [protected]
```

Background worker for focusing [NFOV 2](#)

5.21.4.4 GET_STATUS_CMD

```
string RCCM.NFOVLensController.GET_STATUS_CMD = "ST" [static]
```

Gardasoft command string for getting current status (including output focal power)

5.21.4.5 GET_VOLTAGE_CMD

```
string RCCM.NFOVLensController.GET_VOLTAGE_CMD = "AN3" [static]
```

Gardasoft command string for getting current input voltage

5.21.4.6 manager

```
ControllerManager RCCM.NFOVLensController.manager [protected]
```

Gardasoft controller manager for detecting lens controllers

5.21.4.7 MAX_HEIGHT

```
double RCCM.NFOVLensController.MAX_HEIGHT = (double)Program.Settings.json["distance sensor"]["max height"] [static]
```

Maximum height value to send when reading is out of range

5.21.4.8 MIN_HEIGHT

```
double RCCM.NFOVLensController.MIN_HEIGHT = (double)Program.Settings.json["distance sensor"]["min height"] [static]
```

Minimum height value to send when reading is out of range

5.21.4.9 PARSE_GET

```
Regex RCCM.NFOVLensController.PARSE_GET = new Regex(@"Ig([0-9]+)") [static]
```

Regex for parsing get status command response for input voltage

5.21.4.10 PARSE_GETOUTPUT

```
Regex RCCM.NFOVLensController.PARSE_GETOUTPUT = new Regex(@"AF\s)+([0-9.-]+)") [static]
```

Regex for parsing status command for output focal power

5.21.4.11 read

```
bool RCCM.NFOVLensController.read [protected]
```

Flag to indicate if input power should be read

5.21.4.12 readHeight1ThreadExited

```
AutoResetEvent RCCM.NFOVLensController.readHeight1ThreadExited [protected]
```

Event handler for when [NFOV 1](#) background thread exits

5.21.4.13 readHeight2ThreadExited

```
AutoResetEvent RCCM.NFOVLensController.readHeight2ThreadExited [protected]
```

Event handler for when [NFOV 2](#) background thread exits

5.21.4.14 readThread1Paused

```
bool RCCM.NFOVLensController.readThread1Paused [protected]
```

Flag to indicate to background thread if it should autofocus [NFOV 1](#)

5.21.4.15 readThread2Paused

```
bool RCCM.NFOVLensController.readThread2Paused [protected]
```

Flag to indicate to background thread if it should autofocus [NFOV 2](#)

5.21.4.16 SET_FOCALPOWER_CMD

```
string RCCM.NFOVLensController.SET_FOCALPOWER_CMD = "RS1" [static]
```

Gardasoft command string for setting output focal power

5.21.4.17 UPDATE_PERIOD

```
long RCCM.NFOVLensController.UPDATE_PERIOD = (long)Program.Settings.json["distance sensor"]["focus  
update period"] [static]
```

Setting for period between focal power updates

5.21.5 Property Documentation

5.21.5.1 conversion1

```
double [] RCCM.NFOVLensController.conversion1 [get]
```

Slope, y-intercept of conversion from input voltage to distance ([NFOV 1](#))

5.21.5.2 conversion2

```
double [] RCCM.NFOVLensController.conversion2 [get]
```

Slope, y-intercept of conversion from input voltage to distance ([NFOV 2](#))

5.21.5.3 FocusOffset1

```
double RCCM.NFOVLensController.FocusOffset1 [get], [set]
```

Adjustment offset to add to output focal power for [NFOV 1](#)

5.21.5.4 FocusOffset2

```
double RCCM.NFOVLensController.FocusOffset2 [get], [set]
```

Adjustment offset to add to output focal power for [NFOV 2](#)

5.21.5.5 Height1

```
double RCCM.NFOVLensController.Height1 [get]
```

Current height reading for [NFOV 1](#)

5.21.5.6 Height2

`double RCCM.NFOVLensController.Height2 [get]`

Current height reading for [NFOV 2](#)

5.21.5.7 Motor1

`TrioStepperZMotor RCCM.NFOVLensController.Motor1 [get], [set]`

Z motor for [NFOV 1](#)

5.21.5.8 Motor2

`TrioStepperZMotor RCCM.NFOVLensController.Motor2 [get], [set]`

Z motor for [NFOV 2](#)

5.21.5.9 NFOV1Calibration

`double [,] RCCM.NFOVLensController.NFOV1Calibration [get]`

Array of input voltage, output focal power pairs to interpolate for [NFOV 1](#)

5.21.5.10 NFOV1Controller

`IController RCCM.NFOVLensController.NFOV1Controller [get]`

Controller interface for [NFOV 1](#)

5.21.5.11 NFOV2Calibration

`double [,] RCCM.NFOVLensController.NFOV2Calibration [get]`

Array of input voltage, output focal power pairs to interpolate for [NFOV 2](#)

5.21.5.12 NFOV2Controller

`IController RCCM.NFOVLensController.NFOV2Controller [get]`

Controller interface for [NFOV 2](#)


The documentation for this class was generated from the following file:

- `RCCM/NFOVLensController.cs`

5.22 RCCM.UI.NFOVViewForm Class Reference

Form for displaying [NFOV](#) live image and measurement overlay

Inheritance diagram for `RCCM.UI.NFOVViewForm`:



Public Member Functions

- [NFOVViewForm](#) ([RCCMSystem](#) rccm, [NFOV](#) camera, [ObservableCollection](#)< [MeasurementSequence](#) > cracks)
Initialize [NFOV](#) display
- void [createSegment](#) ()
Create segment that was being drawn by user with mouse input. This will add a point or segment to the active [MeasurementSequence](#)
- void [moveDrawnLineEnd](#) (int x, int y, int w, int h)
Move the end point of the line segment that user is currently drawing
- void [createDrawnLine](#) (int x, int y, int w, int h)
Begin drawing new segment in active [MeasurementSequence](#) from user mouse input
- void [createPoint](#) (int x, int y, int w, int h)
Create new point in active measurement sequence at mouse location

Protected Member Functions

- override void [Dispose](#) (bool disposing)
Clean up any resources being used.

Protected Attributes

- readonly [RCCMSystem](#) rccm
The [RCCM](#) system object. Used for calculating [NFOV](#) position
- readonly [ObservableCollection](#)< [MeasurementSequence](#) > cracks
List of cracks that are being measured
- readonly [NFOV](#) camera
[NFOV](#) camera that is displayed by this window
- [RCCMStage](#) stage
Parent stage of this camera
- [PointF](#) drawnLineStart
Point where line user is drawing begins
- [PointF](#) drawnLineEnd
Point where line user is drawing ends
- [Timer](#) nfovRepaintTimer
Timer for calling [NFOV](#) display repaint

Properties

- int [ActiveIndex](#) [get, set]
Currently selected crack index. The selected crack will be edited by other controls
- int [ActivePoint](#) [get, set]
Currently selected point in *ListPoints*. This point is indicated in the image display
- float [displayScale](#) [get]
Ratio of picture box size to actual [NFOV](#) image dimensions
- bool [Drawing](#) [get]
Indicates whether or not user is drawing a line with mouse

5.22.1 Detailed Description

Form for displaying [NFOV](#) live image and measurement overlay

5.22.2 Constructor & Destructor Documentation

5.22.2.1 NFOVViewForm()

```
RCCM.UI.NFOVViewForm.NFOVViewForm (
    RCCMSystem rccm,
    NFOV camera,
    ObservableCollection< MeasurementSequence > cracks )
```

Initialize [NFOV](#) display

Parameters

<i>rccm</i>	RCCMSystem object, needed for getting location and zoom status
<i>camera</i>	NFOV camera to display
<i>cracks</i>	List of cracks to display

5.22.3 Member Function Documentation

5.22.3.1 createDrawnLine()

```
void RCCM.UI.NFOVViewForm.createDrawnLine (
    int x,
    int y,
    int w,
    int h )
```

Begin drawing new segment in active [MeasurementSequence](#) from user mouse input

Parameters

<i>x</i>	Mouse x location in pixels
<i>y</i>	Mouse y location in pixels
<i>w</i>	Canvas width in pixels
<i>h</i>	Canvas height in pixels

5.22.3.2 createPoint()

```
void RCCM.UI.NFOVViewForm.createPoint (
    int x,
    int y,
    int w,
    int h )
```

Create new point in active measurement sequence at mouse location

Parameters

<i>x</i>	Mouse x location in pixels
<i>y</i>	Mouse y location in pixels
<i>w</i>	Canvas width in pixels
<i>h</i>	Canvas height in pixels

5.22.3.3 createSegment()

```
void RCCM.UI.NFOVViewForm.createSegment ( )
```

Create segment that was being drawn by user with mouse input. This will add a point or segment to the active [MeasurementSequence](#)

5.22.3.4 Dispose()

```
override void RCCM.UI.NFOVViewForm.Dispose (
    bool disposing ) [protected]
```

Clean up any resources being used.

Parameters

<i>disposing</i>	true if managed resources should be disposed; otherwise, false.
------------------	---

5.22.3.5 moveDrawnLineEnd()

```
void RCCM.UI.NFOVViewForm.moveDrawnLineEnd (
    int x,
    int y,
    int w,
    int h )
```

Move the end point of the line segment that user is currently drawing

Parameters

<i>x</i>	Mouse x location in pixels
<i>y</i>	Mouse y location in pixels
<i>w</i>	Canvas width in pixels
<i>h</i>	Canvas height in pixels

5.22.4 Member Data Documentation

5.22.4.1 camera

```
readonly NFOV RCCM.UI.NFOVViewForm.camera [protected]
```

[NFOV](#) camera that is displayed by this window

5.22.4.2 cracks

```
readonly ObservableCollection<MeasurementSequence> RCCM.UI.NFOVViewForm.cracks [protected]
```

List of cracks that are being measured

5.22.4.3 drawnLineEnd

```
PointF RCCM.UI.NFOVViewForm.drawnLineEnd [protected]
```

Point where line user is drawing ends

5.22.4.4 drawnLineStart

```
PointF RCCM.UI.NFOVViewForm.drawnLineStart [protected]
```

Point where line user is drawing begins

5.22.4.5 nfovRepaintTimer

Timer RCCM.UI.NFOVViewForm.nfovRepaintTimer [protected]

Timer for calling [NFOV](#) display repaint

5.22.4.6 rccm

readonly [RCCMSystem](#) RCCM.UI.NFOVViewForm.rccm [protected]

The [RCCM](#) system object. Used for calculating [NFOV](#) position

5.22.4.7 stage

[RCCMStage](#) RCCM.UI.NFOVViewForm.stage [protected]

Parent stage of this camera

5.22.5 Property Documentation

5.22.5.1 ActiveIndex

int RCCM.UI.NFOVViewForm.ActiveIndex [get], [set], [protected]

Currently selected crack index. The selected crack will be edited by other controls

5.22.5.2 ActivePoint

int RCCM.UI.NFOVViewForm.ActivePoint [get], [set], [protected]

Currently selected point in ListPoints. This point is indicated in the image display

5.22.5.3 displayScale

float RCCM.UI.NFOVViewForm.displayScale [get], [protected]

Ratio of picture box size to actual [NFOV](#) image dimensions

5.22.5.4 Drawing

```
bool RCCM.UI.NFOVViewForm.Drawing [get], [protected]
```

Indicates whether or not user is drawing a line with mouse

The documentation for this class was generated from the following files:

- [RCCM/UI/NFOVViewForm.cs](#)
- [RCCM/UI/NFOVViewForm.Designer.cs](#)

5.23 RCCM.PanelView Class Reference

Object used to draw panel graphic to show location of stages

Public Member Functions

- [PanelView](#) ([RCCMSystem rccm](#))
Initialize panel view
- void [Paint](#) ([Graphics g](#))
Paint panel, stages, and position crosshair graphics
- void [SetTransform](#) ([Graphics g](#))
Create the transform matrix to map pixel coordinates to the global coordinate system

Protected Attributes

- readonly [RCCMSystem rccm](#)
Reference to [RCCMSystem](#) object
- Pen [pen](#)
Pen for drawing lines
- Brush [panelBrush](#)
Brush defining style for drawing panel rectangle
- Brush [coarseBrush](#)
Brush defining style for drawing coarse stage rectangle
- Brush [fineBrush](#)
Brush defining style for drawing fine stage rectangles
- RectangleF [panel](#)
Rectangle defining dimensions of panel
- RectangleF [coarse](#)
Rectangle defining dimensions of coarse stage travel region
- RectangleF [fine1](#)
Rectangle defining dimensions of fine 1 stage travel region
- RectangleF [fine2](#)
Rectangle defining dimensions of fine 1 stage travel region
- SizeF [fine1Offset](#)
Position offset to fine 1 rectangle top left corner
- SizeF [fine2Offset](#)
Position offset to fine 2 rectangle top left corner
- Matrix [transform](#)

Graphics transform mapping pixels to global coordinate system

- float [coarseXPos](#)

Coarse X actuator position

- float [coarseYPos](#)

Coarse Y actuator position

- float [fine1XPos](#)

Fine 1 X actuator position

- float [fine1YPos](#)

Fine 1 Y actuator position

- float [fine2XPos](#)

Fine 2 X actuator position

- float [fine2YPos](#)

Fine 2 Y actuator position

5.23.1 Detailed Description

Object used to draw panel graphic to show location of stages

5.23.2 Constructor & Destructor Documentation

5.23.2.1 PanelView()

```
RCCM.PanelView.PanelView (
    RCCMSystem rccm )
```

Initialize panel view

Parameters

<i>rccm</i>	Reference to RCCM object
-------------	--

5.23.3 Member Function Documentation

5.23.3.1 Paint()

```
void RCCM.PanelView.Paint (
    Graphics g )
```

Paint panel, stages, and position crosshair graphics

Parameters

<i>g</i>	The graphics object representing the control on which to draw
<i>rccm</i>	Handle to RCCMSystem object. Will be used to get positions

5.23.3.2 SetTransform()

```
void RCCM.PanelView.SetTransform (
    Graphics g )
```

Create the transform matrix to map pixel coordinates to the global coordinate system

Parameters

<i>g</i>	The graphics object representing the control on which to draw
----------	---

5.23.4 Member Data Documentation

5.23.4.1 coarse

```
RectangleF RCCM.PanelView.coarse [protected]
```

Rectangle defining dimensions of coarse stage travel region

5.23.4.2 coarseBrush

```
Brush RCCM.PanelView.coarseBrush [protected]
```

Brush defining style for drawing coarse stage rectangle

5.23.4.3 coarseXPos

```
float RCCM.PanelView.coarseXPos [protected]
```

Coarse X actuator position

5.23.4.4 coarseYPos

```
float RCCM.PanelView.coarseYPos [protected]
```

Coarse Y actuator position

5.23.4.5 fine1

`RectangleF RCCM.PanelView.fine1` [protected]

Rectangle defining dimensions of fine 1 stage travel region

5.23.4.6 fine1Offset

`SizeF RCCM.PanelView.fine1Offset` [protected]

Position offset to fine 1 rectangle top left corner

5.23.4.7 fine1XPos

`float RCCM.PanelView.fine1XPos` [protected]

Fine 1 X actuator position

5.23.4.8 fine1YPos

`float RCCM.PanelView.fine1YPos` [protected]

Fine 1 Y actuator position

5.23.4.9 fine2

`RectangleF RCCM.PanelView.fine2` [protected]

Rectangle defining dimensions of fine 1 stage travel region

5.23.4.10 fine2Offset

`SizeF RCCM.PanelView.fine2Offset` [protected]

Position offset to fine 2 rectangle top left corner

5.23.4.11 fine2XPos

`float RCCM.PanelView.fine2XPos` [protected]

Fine 2 X actuator position

5.23.4.12 fineYPos

`float RCCM.PanelView.fineYPos` [protected]

Fine 2 Y actuator position

5.23.4.13 fineBrush

`Brush RCCM.PanelView.fineBrush` [protected]

Brush defining style for drawing fine stage rectangles

5.23.4.14 panel

`RectangleF RCCM.PanelView.panel` [protected]

Rectangle defining dimensions of panel

5.23.4.15 panelBrush

`Brush RCCM.PanelView.panelBrush` [protected]

Brush defining style for drawing panel rectangle

5.23.4.16 pen

`Pen RCCM.PanelView.pen` [protected]

Pen for drawing lines

5.23.4.17 rccm

`readonly RCCMSystem RCCM.PanelView.rccm` [protected]

Reference to [RCCMSystem](#) object

5.23.4.18 transform

`Matrix RCCM.PanelView.transform` [protected]

Graphics transform mapping pixels to global coordinate system


The documentation for this class was generated from the following file:

- `RCCM/PanelView.cs`

5.24 RCCM.UI.PluginInitializationForm Class Reference

Form for starting plugin and entering inputs

Inheritance diagram for RCCM.UI.PluginInitializationForm:



Public Member Functions

- [PluginInitializationForm](#) ([RCCMSystem](#) rccm, [IRCCMPlugin](#) plugin)
Open form for given plugin

Protected Member Functions

- override void [Dispose](#) (bool disposing)
Clean up any resources being used.

Protected Attributes

- readonly [RCCMSystem](#) **rccm**
- readonly [IRCCMPlugin](#) **plugin**
- [IRCCMPluginActor](#) **actor**
- [TableLayoutPanel](#) **tableLayoutPanelParams**
- [Dictionary](#)< string, [TextBox](#) > **parameterControls**

5.24.1 Detailed Description

Form for starting plugin and entering inputs

5.24.2 Constructor & Destructor Documentation

5.24.2.1 PluginInitializationForm()

```

RCCM.UI.PluginInitializationForm.PluginInitializationForm (
    RCCMSystem rccm,
    IRCCMPlugin plugin )
  
```

Open form for given plugin

Parameters

<i>rccm</i>	Reference to RCCM object
<i>plugin</i>	Plugin to be started from this form

5.24.3 Member Function Documentation

5.24.3.1 Dispose()

```
override void RCCM.UI.PluginInitializationForm.Dispose (
    bool disposing ) [protected]
```

Clean up any resources being used.

Parameters

<i>disposing</i>	true if managed resources should be disposed; otherwise, false.
------------------	---


The documentation for this class was generated from the following files:

- [RCCM/UI/PluginInitializationForm.cs](#)
- [RCCM/UI/PluginInitializationForm.Designer.cs](#)

5.25 PressureCameraTrigger.PressureCameraTrigger Class Reference

Captures images when trigger pressure is reached

Inheritance diagram for PressureCameraTrigger.PressureCameraTrigger:



Public Member Functions

- [PressureCameraTrigger](#) ([RCCMSystem](#) rccm, Dictionary< string, string > parameters)
Create plugin actor from parameter strings
- void [Run](#) ()
Continuously read pressure and capture image when threshold is passed
- void [Stop](#) ()
This function should cause the plugin to stop as soon as possible

Protected Attributes

- readonly [ICamera](#) **camera**
- string **path**
- double **triggerPressure**
- bool **ascending**
- readonly [RCCMSystem](#) **rccm**

Properties

- bool **Running** [get, protected set]

5.25.1 Detailed Description

Captures images when trigger pressure is reached

5.25.2 Constructor & Destructor Documentation

5.25.2.1 PressureCameraTrigger()

```
PressureCameraTrigger.PressureCameraTrigger.PressureCameraTrigger (
    RCCMSystem rccm,
    Dictionary< string, string > parameters )
```

Create plugin actor from parameter strings

Parameters

<i>rccm</i>	Reference to RCCM object
<i>parameters</i>	Map of test parameters to values

5.25.3 Member Function Documentation

5.25.3.1 Run()

```
void PressureCameraTrigger.PressureCameraTrigger.Run ( )
```

Continuously read pressure and capture image when threshold is passed

Implements [RCCM.IRCCMPluginActor](#).

5.25.3.2 Stop()

```
void PressureCameraTrigger.PressureCameraTrigger.Stop ( )
```

This function should cause the plugin to stop as soon as possible


Implements [RCCM.IRCCMPluginActor](#).

The documentation for this class was generated from the following file:

- `RCCM/Plugins/PressureCameraTrigger/PressureCameraTrigger/PressureCameraTrigger.cs`

5.26 PressureCameraTrigger.PressureCameraTriggerPlugin Class Reference

Inheritance diagram for PressureCameraTrigger.PressureCameraTriggerPlugin:



Public Member Functions

- [IRCCMPluginActor Instance](#) ([RCCMSystem](#) rccm, Dictionary< string, string > parameters)
Create plugin with given test parameters

Static Public Attributes

- static double [PERIOD](#) = 50
Time period of a single loop iteration

Properties

- string [Name](#) [get]
Publicly visible plugin name
- string [] [Params](#) [get]
User entered test inputs

5.26.1 Member Function Documentation

5.26.1.1 Instance()

```
IRCCMPluginActor PressureCameraTrigger.PressureCameraTriggerPlugin.Instance (
    RCCMSystem rccm,
    Dictionary< string, string > parameters )
```

Create plugin with given test parameters

Parameters

<i>rccm</i>	
<i>parameters</i>	User entered test parameters

Returns

Implements [RCCM.IRCCMPlugin](#).

5.26.2 Member Data Documentation**5.26.2.1 PERIOD**

```
double PressureCameraTrigger.PressureCameraTriggerPlugin.PERIOD = 50 [static]
```

Time period of a single loop iteration

5.26.3 Property Documentation**5.26.3.1 Name**

```
string PressureCameraTrigger.PressureCameraTriggerPlugin.Name [get]
```

Publicly visible plugin name

5.26.3.2 Params

```
string [] PressureCameraTrigger.PressureCameraTriggerPlugin.Params [get]
```

User entered test inputs


The documentation for this class was generated from the following file:

- `RCCM/Plugins/PressureCameraTrigger/PressureCameraTrigger/PressureCameraTriggerPlugin.cs`

5.27 RCCM.UI.RCCMMainForm Class Reference

The main window of the program from which all hardware initialization and termination is directed

Inheritance diagram for RCCM.UI.RCCMMainForm:



Classes

- class **NativeMethods**
Helper class for preventing OS from putting computer in sleep mode

Public Member Functions

- [RCCMMainForm](#) (ICollection< [IRCCMPlugin](#) > plugins)
Create the main form and initialize all hardware
- void [applyUISettings](#) ()
Set increment of position controls to actuator step value

Protected Member Functions

- override void [Dispose](#) (bool disposing)
Clean up any resources being used.

Protected Attributes

- [RCCMSystem](#) rccm
The main object representing the [RCCM](#) containing references to all hardware
- bool [nfov1Open](#)
Flag for indicating if NFOV1 form is open
- bool [nfov2Open](#)
Flag for indicating if NFOV2 form is open
- bool [wfov1Open](#)
Flag for indicating if WFOV1 form is open
- bool [wfov2Open](#)
Flag for indicating if WFOV2 form is open
- Timer [panelRepaintTimer](#)
Timer for replotting certain panel graphic
- ObservableCollection< [MeasurementSequence](#) > [cracks](#)
List of measurement objects. Observable so controls can update when other forms update them
- [TestResults](#) test
Object for managing test result plotting
- [PanelView](#) view
Object for managing panel graphic drawing
- ComponentResourceManager [resources](#)
Resource manager for loading ActiveX object for Trio controller
- AxTrioPCLib.AxTrioPC [trioPC](#)
ActiveX control for trio controller
- uint [fPreviousExecutionState](#)
Holds sleep setting of computer before starting program so it can be reverted on exit

5.27.1 Detailed Description

The main window of the program from which all hardware initialization and termination is directed

5.27.2 Constructor & Destructor Documentation

5.27.2.1 RCCMMainForm()

```
RCCM.UI.RCCMMainForm.RCCMMainForm (
    ICollection< IRCCMPlugin > plugins )
```

Create the main form and initialize all hardware

Parameters

<i>plugins</i>	List of plugins that were found on startup
----------------	--

5.27.3 Member Function Documentation

5.27.3.1 applyUISettings()

```
void RCCM.UI.RCCMMainForm.applyUISettings ( )
```

Set increment of position controls to actuator step value

5.27.3.2 Dispose()

```
override void RCCM.UI.RCCMMainForm.Dispose (
    bool disposing ) [protected]
```

Clean up any resources being used.

Parameters

<i>disposing</i>	true if managed resources should be disposed; otherwise, false.
------------------	---

5.27.4 Member Data Documentation

5.27.4.1 cracks

ObservableCollection<MeasurementSequence> RCCM.UI.RCCMMainForm.cracks [protected]

List of measurement objects. Observable so controls can update when other forms update them

5.27.4.2 fPreviousExecutionState

uint RCCM.UI.RCCMMainForm.fPreviousExecutionState [protected]

Holds sleep setting of computer before starting program so it can be reverted on exit

5.27.4.3 nfov1Open

bool RCCM.UI.RCCMMainForm.nfov1Open [protected]

Flag for indicating if NFOV1 form is open

5.27.4.4 nfov2Open

bool RCCM.UI.RCCMMainForm.nfov2Open [protected]

Flag for indicating if NFOV2 form is open

5.27.4.5 panelRepaintTimer

Timer RCCM.UI.RCCMMainForm.panelRepaintTimer [protected]

Timer for replotting certain panel graphic

5.27.4.6 rccm

RCCMSystem RCCM.UI.RCCMMainForm.rccm [protected]

The main object representing the [RCCM](#) containing references to all hardware

5.27.4.7 resources

ComponentResourceManager RCCM.UI.RCCMMainForm.resources [protected]

Resource manager for loading ActiveX object for Trio controller

5.27.4.8 test

`TestResults` `RCCM.UI.RCCMMainForm.test` [protected]

Object for managing test result plotting

5.27.4.9 triopc

`AxTrioPCLib.AxTrioPC` `RCCM.UI.RCCMMainForm.triopc` [protected]

ActiveX control for trio controller

5.27.4.10 view

`PanelView` `RCCM.UI.RCCMMainForm.view` [protected]

Object for managing panel graphic drawing

5.27.4.11 wfov1Open

`bool` `RCCM.UI.RCCMMainForm.wfov1Open` [protected]

Flag for indicating if WFOV1 form is open

5.27.4.12 wfov2Open

`bool` `RCCM.UI.RCCMMainForm.wfov2Open` [protected]

Flag for indicating if WFOV2 form is open

The documentation for this class was generated from the following files:

- `RCCM/UI/RCCMMainForm.cs`
- `RCCM/UI/RCCMMainForm.Designer.cs`

5.28 RCCM.RCCMPluginLoader Class Reference

Plugin loading framework from <https://code.msdn.microsoft.com/windowsdesktop/Creating-a-simple-plugin-b6174b62>

Static Public Member Functions

- static `ICollection< IRCCMPlugin >` `LoadPlugins` (string path)
Load plugin dlls from specified path

5.28.1 Detailed Description

Plugin loading framework from <https://code.msdn.microsoft.com/windowsdesktop/Creating-a-simple-plugin-b6174b62>

5.28.2 Member Function Documentation

5.28.2.1 LoadPlugins()

```
static ICollection<IRCCMPlugin> RCCM.RCCMPluginLoader.LoadPlugins (
    string path ) [static]
```

Load plugin dlls from specified path

Parameters

<i>path</i>	Path where program should search for plugin dlls
-------------	--

Returns

List of plugin interfaces

The documentation for this class was generated from the following file:

- RCCM/RCCMPluginLoader.cs

5.29 RCCM.RCCMSystem Class Reference

Object representing all the hardware and definitions for the [RCCM](#)

Public Member Functions

- [RCCMSystem](#) (AxTrioPC axTrioPC)
Create [RCCM](#) object and initialize all hardware
- double [GetPanelDistance](#) (double panelX, double panelY)
Calculate expected distance to panel from distance sensor at a given point
- PointF [GetNFOVLocation](#) ([RCCMStage](#) stage, [CoordinateSystem](#) sys)
Get position of [NFOV](#) camera in specified coordinate system
- PointF [GetWFOVLocation](#) ([RCCMStage](#) stage, [CoordinateSystem](#) sys)
Get position of [WFOV](#) camera in specified coordinate system
- PointF [FineVectorToGlobalVector](#) (double x, double y)
Convert position relative to rotation plate to global coordinate system vector
- PointF [GlobalVectorToPanelVector](#) (double x, double y)
Convert position in global coordinate system to panel coordinates
- void [ApplyMotorSettings](#) ()
Apply all defined settings for all axes
- void [SaveMotorSettings](#) ()
Save motor settings to [Settings](#) object
- async Task [Stop](#) ()
Perform any action necessary to disconnect from hardware

Static Public Attributes

- static string [] **AXES** = new string[8] { "coarse X", "coarse Y", "fine 1 X", "fine 1 Y", "fine 1 Z", "fine 2 X", "fine 2 Y", "fine 2 Z" }

*String keys used to represent actuators in settings and **Motor** dictionary*

Protected Member Functions

- void **setFineStageRotationMatrix** ()
When FineStageAngle is updated, this function is called to update rotation matrix
- void **setPanelRotationMatrix** ()
When PanelAngle is updated, this function is called to update rotation matrix

Protected Attributes

- double [,] **fineStageRotation**
- double [,] **panelRotation**

Properties

- **NFOV NFOV1** [get]
Narrow field of view camera on the first set of fine axes
- **NFOV NFOV2** [get]
Narrow field of view camera on the second set of fine axes
- **WFOV WFOV1** [get]
Wide field of view camera on the first set of fine axes
- **WFOV WFOV2** [get]
Wide field of view camera on the second set of fine axes
- **NFOVLensController LensController** [get]
*Object for autofocusing **NFOV** lenses based on distance sensor input*
- Dictionary< string, **Motor** > **motors** [get]
Dictionary mapping string keys to motor objects
- **ICycleCounter Counter** [get]
Interface to a real or virtual cycle counter / pressure input
- double **FineStageAngle** [get, set]
Angle of fine stage beam on rotation plate. Changing this value also updates settings
- double **PanelAngle** [get, set]
Angle of panel with respect to coarse axes. Changing this value also updates settings
- double **PanelOffsetX** [get, set]
Axial offset of panel from corner of coarse axis travel region. Changing this value also updates settings
- double **PanelOffsetY** [get, set]
Hoop offset of panel from corner of coarse axis travel region. Changing this value also updates settings
- double **PanelWidth** [get, set]
Axial dimension of panel. Changing this value also updates settings
- double **PanelHeight** [get, set]
Hoop dimension of panel. Changing this value also updates settings
- double **PanelRadius** [get, set]
Radius of curvature of panel. Changing this value also updates settings
- double **NFOV1X** [get, set]

- *Offset of NFOV1 from center of rotation plate along beam. Changing this value also updates settings*
 • double [NFOV1Y](#) [get, set]
- *Offset of NFOV1 from center of rotation plate perpindicular to beam. Changing this value also updates settings*
 • double [NFOV2X](#) [get, set]
- *Offset of NFOV2 from center of rotation plate along beam. Changing this value also updates settings*
 • double [NFOV2Y](#) [get, set]
- *Offset of NFOV2 from center of rotation plate perpindicular to beam. Changing this value also updates settings*
 • double [WFOV1X](#) [get, set]
- *Offset of WFOV1 from center of rotation plate along beam. Changing this value also updates settings*
 • double [WFOV1Y](#) [get, set]
- *Offset of WFOV1 from center of rotation plate perpindicular to beam. Changing this value also updates settings*
 • double [WFOV2X](#) [get, set]
- *Offset of WFOV2 from center of rotation plate along beam. Changing this value also updates settings*
 • double [WFOV2Y](#) [get, set]
- *Offset of WFOV2 from center of rotation plate perpindicular to beam. Changing this value also updates settings*
 • [TrioController trioPC](#) [get]
- *Helper object for sending commands to trio controller*

5.29.1 Detailed Description

Object representing all the hardware and definitions for the [RCCM](#)

5.29.2 Constructor & Destructor Documentation

5.29.2.1 RCCMSysSystem()

```
RCCM.RCCMSysSystem.RCCMSysSystem (
    AxTrioPC axTrioPC )
```

Create [RCCM](#) object and initialize all hardware

Parameters

axTrioPC	ActiveX control for communicating with Trio controller
--------------------------	--

5.29.3 Member Function Documentation

5.29.3.1 ApplyMotorSettings()

```
void RCCM.RCCMSysSystem.ApplyMotorSettings ( )
```

Apply all defined settings for all axes

5.29.3.2 FineVectorToGlobalVector()

```
PointF RCCM.RCCMSystem.FineVectorToGlobalVector (
    double x,
    double y )
```

Convert position relative to rotation plate to global coordinate system vector

Parameters

<i>x</i>	Position along fine stage beam
<i>y</i>	Position perpendicular to fine stage beam

Returns

PointF with X and Y coordinates in global frame

5.29.3.3 GetNFOVLocation()

```
PointF RCCM.RCCMSystem.GetNFOVLocation (
    RCCMStage stage,
    CoordinateSystem sys )
```

Get position of **NFOV** camera in specified coordinate system

Parameters

<i>stage</i>	Enum value corresponding to desired camera
<i>sys</i>	Enum value corresponding to desired coordinate system

Returns

PointF with X and Y coordinates of camera

5.29.3.4 GetPanelDistance()

```
double RCCM.RCCMSystem.GetPanelDistance (
    double panelX,
    double panelY )
```

Calculate expected distance to panel from distance sensor at a given point

Parameters

<i>panelX</i>	X coordinate on panel
<i>panelY</i>	Y coordinate on panel

Returns

Distance to panel - may be negative

5.29.3.5 GetWFOVLocation()

```
PointF RCCM.RCCMSystem.GetWFOVLocation (
    RCCMStage stage,
    CoordinateSystem sys )
```

Get position of [WFOV](#) camera in specified coordinate system

Parameters

<i>stage</i>	Enum value corresponding to desired camera
<i>sys</i>	Enum value corresponding to desired coordinate system

Returns

PointF with X and Y coordinates of camera

5.29.3.6 GlobalVectorToPanelVector()

```
PointF RCCM.RCCMSystem.GlobalVectorToPanelVector (
    double x,
    double y )
```

Convert position in global coordinate system to panel coordinates

Parameters

<i>x</i>	Position along coarse axial direction
<i>y</i>	Position along coarse hoop direction

Returns

PointF with X and Y coordinates in panel frame

5.29.3.7 SaveMotorSettings()

```
void RCCM.RCCMSystem.SaveMotorSettings ( )
```

Save motor settings to [Settings](#) object

5.29.3.8 setFineStageRotationMatrix()

```
void RCCM.RCCMSystem.setFineStageRotationMatrix ( ) [protected]
```

When FineStageAngle is updated, this function is called to update rotation matrix

5.29.3.9 setPanelRotationMatrix()

```
void RCCM.RCCMSystem.setPanelRotationMatrix ( ) [protected]
```

When PanelAngle is updated, this function is called to update rotation matrix

5.29.3.10 Stop()

```
async Task RCCM.RCCMSystem.Stop ( )
```

Perform any action necessary to disconnect from hardware

Returns

Task completion

5.29.4 Member Data Documentation

5.29.4.1 AXES

```
string [ ] RCCM.RCCMSystem.AXES = new string[8] { "coarse X", "coarse Y", "fine 1 X", "fine 1  
Y", "fine 1 Z", "fine 2 X", "fine 2 Y", "fine 2 Z" } [static]
```

String keys used to represent actuators in settings and [Motor](#) dictionary

5.29.5 Property Documentation

5.29.5.1 Counter

```
ICycleCounter RCCM.RCCMSystem.Counter [get]
```

Interface to a real or virtual cycle counter / pressure input

5.29.5.2 FineStageAngle

`double RCCM.RCCMSysytem.FineStageAngle [get], [set]`

Angle of fine stage beam on rotation plate. Changing this value also updates settings

5.29.5.3 LensController

`NFOVLensController RCCM.RCCMSysytem.LensController [get]`

Object for autofocusing [NFOV](#) lenses based on distance sensor input

5.29.5.4 motors

`Dictionary<string, Motor> RCCM.RCCMSysytem.motors [get]`

Dictionary mapping string keys to motor objects

5.29.5.5 NFOV1

`NFOV RCCM.RCCMSysytem.NFOV1 [get]`

Narrow field of view camera on the first set of fine axes

5.29.5.6 NFOV1X

`double RCCM.RCCMSysytem.NFOV1X [get], [set]`

Offset of NFOV1 from center of rotation plate along beam. Changing this value also updates settings

5.29.5.7 NFOV1Y

`double RCCM.RCCMSysytem.NFOV1Y [get], [set]`

Offset of NFOV1 from center of rotation plate perpendicular to beam. Changing this value also updates settings

5.29.5.8 NFOV2

`NFOV RCCM.RCCMSysytem.NFOV2 [get]`

Narrow field of view camera on the second set of fine axes

5.29.5.9 NFOV2X

```
double RCCM.RCCMSystem.NFOV2X [get], [set]
```

Offset of NFOV2 from center of rotation plate along beam. Changing this value also updates settings

5.29.5.10 NFOV2Y

```
double RCCM.RCCMSystem.NFOV2Y [get], [set]
```

Offset of NFOV2 from center of rotation plate perpendicular to beam. Changing this value also updates settings

5.29.5.11 PanelAngle

```
double RCCM.RCCMSystem.PanelAngle [get], [set]
```

Angle of panel with respect to coarse axes. Changing this value also updates settings

5.29.5.12 PanelHeight

```
double RCCM.RCCMSystem.PanelHeight [get], [set]
```

Hoop dimension of panel. Changing this value also updates settings

5.29.5.13 PanelOffsetX

```
double RCCM.RCCMSystem.PanelOffsetX [get], [set]
```

Axial offset of panel from corner of coarse axis travel region. Changing this value also updates settings

5.29.5.14 PanelOffsetY

```
double RCCM.RCCMSystem.PanelOffsetY [get], [set]
```

Hoop offset of panel from corner of coarse axis travel region. Changing this value also updates settings

5.29.5.15 PanelRadius

```
double RCCM.RCCMSystem.PanelRadius [get], [set]
```

Radius of curvature of panel. Changing this value also updates settings

5.29.5.16 PanelWidth

`double RCCM.RCCMSysSystem.PanelWidth [get], [set]`

Axial dimension of panel. Changing this value also updates settings

5.29.5.17 triopc

`TrioController RCCM.RCCMSysSystem.triopc [get]`

Helper object for sending commands to trio controller

5.29.5.18 WFOV1

`WFOV RCCM.RCCMSysSystem.WFOV1 [get]`

Wide field of view camera on the first set of fine axes

5.29.5.19 WFOV1X

`double RCCM.RCCMSysSystem.WFOV1X [get], [set]`

Offset of WFOV1 from center of rotation plate along beam. Changing this value also updates settings

5.29.5.20 WFOV1Y

`double RCCM.RCCMSysSystem.WFOV1Y [get], [set]`

Offset of WFOV1 from center of rotation plate perpendicular to beam. Changing this value also updates settings

5.29.5.21 WFOV2

`WFOV RCCM.RCCMSysSystem.WFOV2 [get]`

Wide field of view camera on the second set of fine axes

5.29.5.22 WFOV2X

`double RCCM.RCCMSysSystem.WFOV2X [get], [set]`

Offset of WFOV2 from center of rotation plate along beam. Changing this value also updates settings

5.29.5.23 WFOV2Y

```
double RCCM.RCCMSystem.WFOV2Y [get], [set]
```


Offset of WFOV2 from center of rotation plate perpendicular to beam. Changing this value also updates settings

The documentation for this class was generated from the following file:

- RCCM/RCCMSystem.cs

5.30 RepeatabilityTest.RepeatabilityTest Class Reference

Inheritance diagram for RepeatabilityTest.RepeatabilityTest:



Public Member Functions

- **RepeatabilityTest** ([RCCMSystem](#) rccm, Dictionary< string, string > parameters)
- void [Run](#) ()
Run the function with the inputs already passed to the plugin
- void [Stop](#) ()
This function should cause the plugin to stop as soon as possible

Protected Attributes

- readonly [ICamera](#) camera
- readonly [Motor](#) motor
- string path
- int repetitions
- double distance
- readonly [RCCMSystem](#) rccm
- Thread testThread

Properties

- bool **Running** [get, protected set]

5.30.1 Member Function Documentation

5.30.1.1 Run()

```
void RepeatabilityTest.RepeatabilityTest.Run ( )
```

Run the function with the inputs already passed to the plugin

Implements [RCCM.IRCCMPluginActor](#).

5.30.1.2 Stop()

```
void RepeatabilityTest.RepeatabilityTest.Stop ( )
```

This function should cause the plugin to stop as soon as possible


Implements [RCCM.IRCCMPluginActor](#).

The documentation for this class was generated from the following file:

- [RCCM/Plugins/RepeatabilityTest/RepeatabilityTest/RepeatabilityTest.cs](#)

5.31 RepeatabilityTest.RepeatabilityTestPlugin Class Reference

Inheritance diagram for RepeatabilityTest.RepeatabilityTestPlugin:



Public Member Functions

- [IRCCMPluginActor Instance](#) ([RCCMSystem](#) rccm, Dictionary< string, string > parameters)
Create an instance of the plugin

Properties

- string **Name** [get]
- string [] **Params** [get]

5.31.1 Member Function Documentation

5.31.1.1 Instance()

```
IRCCMPluginActor RepeatabilityTest.RepeatabilityTestPlugin.Instance (
    RCCMSystem rccm,
    Dictionary< string, string > parameters )
```

Create an instance of the plugin

Parameters

<i>rccm</i>	Reference to the RCCM object
<i>parameters</i>	User inputs to the plugin

Returns

An instance of the runnable plugin interface

Implements [RCCM.IRCCMPlugin](#).

The documentation for this class was generated from the following file:

- [RCCM/Plugins/RepeatabilityTest/RepeatabilityTest/RepeatabilityTestPlugin.cs](#)

5.32 RCCM.Settings Class Reference

Object representing settings json file

Public Member Functions

- [Settings](#) (string filename)
Create settings object from file
- bool [save](#) ()
Save settings to original file they were read from
Returns
True if settings saved successfully, false otherwise
- bool [save](#) (string filename)
Save settings to a specified file

Public Attributes

- string [file](#)
Filename
- JObject [json](#)
Json dictionary of settings

5.32.1 Detailed Description

Object representing settings json file

5.32.2 Constructor & Destructor Documentation**5.32.2.1 Settings()**

```
RCCM.Settings.Settings (
    string filename )
```

Create settings object from file

Parameters

<i>filename</i>	Path to settings json file
-----------------	----------------------------

5.32.3 Member Function Documentation

5.32.3.1 `save()` [1/2]

```
bool RCCM.Settings.save ( )
```

Save settings to original file they were read from

Returns

True if settings saved successfully, false otherwise

5.32.3.2 `save()` [2/2]

```
bool RCCM.Settings.save (
    string filename )
```

Save settings to a specified file

Parameters

<i>filename</i>	Path of file to save to
-----------------	-------------------------

Returns

True if settings saved successfully, false otherwise

5.32.4 Member Data Documentation

5.32.4.1 `file`

```
string RCCM.Settings.file
```

Filename

5.32.4.2 json

`JObject RCCM.Settings.json`

Json dictionary of settings

The documentation for this class was generated from the following file:

- `RCCM/Settings.cs`

5.33 RCCM.TestResults Class Reference

Helper object for plotting test status such as crack lengths and pressure

Public Member Functions

- **TestResults** (`RCCMSystem` rccm, `ObservableCollection< MeasurementSequence >` cracks, `Chart` crackChart, `Chart` cycleChart, `TextBox` cycleIndicator, `TextBox` pressureIndicator, `ListBox` crackSelection)
- `void PlotCracks ()`
Redraw charts

Protected Attributes

- `ObservableCollection< MeasurementSequence >` cracks
List of all cracks being measured by RCCM cameras
- `Chart` crackChart
Chart UI object for plotting crack length
- `Chart` cycleChart
Chart UI object for plotting past pressure readings
- `TextBox` cycleIndicator
Text indicator for cycle number
- `TextBox` pressureIndicator
Text indicator for current pressure reading
- `ListBox` crackSelection
Listbox with selectable crack names determining what to plot
- `ICycleCounter` counter
RCCM cycle counter object
- `Timer` updateControlsTimer
Timer for calling update function for UI
- `int` savedReadings
Number of pressure readings to save and plot

5.33.1 Detailed Description

Helper object for plotting test status such as crack lengths and pressure

5.33.2 Member Function Documentation

5.33.2.1 PlotCracks()

```
void RCCM.TestResults.PlotCracks ( )
```

Redraw charts

5.33.3 Member Data Documentation

5.33.3.1 counter

```
ICycleCounter RCCM.TestResults.counter [protected]
```

RCCM cycle counter object

5.33.3.2 crackChart

```
Chart RCCM.TestResults.crackChart [protected]
```

Chart UI object for plotting crack length

5.33.3.3 cracks

```
ObservableCollection<MeasurementSequence> RCCM.TestResults.cracks [protected]
```

List of all cracks being measured by RCCM cameras

5.33.3.4 crackSelection

```
ListBox RCCM.TestResults.crackSelection [protected]
```

Listbox with selectable crack names determining what to plot

5.33.3.5 cycleChart

```
Chart RCCM.TestResults.cycleChart [protected]
```

Chart UI object for plotting past pressure readings

5.33.3.6 cycleIndicator

`TextBox RCCM.TestResults.cycleIndicator` [protected]

Text indicator for cycle number

5.33.3.7 pressureIndicator

`TextBox RCCM.TestResults.pressureIndicator` [protected]

Text indicator for current pressure reading

5.33.3.8 savedReadings

`int RCCM.TestResults.savedReadings` [protected]

Number of pressure readings to save and plot

5.33.3.9 updateControlsTimer

`Timer RCCM.TestResults.updateControlsTimer` [protected]

Timer for calling update function for [UI](#)

The documentation for this class was generated from the following file:

- `RCCM/TestResults.cs`

5.34 RCCM.TrioController Class Reference

Class representing Trio stepper motor controller

Public Member Functions

- [TrioController](#) (AxTrioPC axTrioPC)
Connect to and initialize Trio controller
- bool [isMoving](#) (short nAxis)
Check if an axis is currently moving
- double [] [GetAllAxisProperties](#) (short nAxis)
Get all axis property values
- double [GetAxisProperty](#) (string property, short nAxis)
Get a specified property of a motor
- bool [SetAxisProperty](#) (string property, double value, short nAxis)
Set a specified property of a motor
- double [GetProperty](#) (string property)
Get property value (could be axis or controller property)
- bool [MoveAbs](#) (short nAxis, double pos)
Move a specified actuator to a new coordinate
- bool [MoveRel](#) (short nAxis, double pos)
Move a specified distance from current actuator position
- bool [Jog](#) (bool fwd, short nAxis)
Begin moving an actuator continuously
- bool [JogStop](#) (short nAxis)
Stop continuous actuator motion
- void [Zero](#) (short nAxis)
Set current actuator position as 0 and clear errors
- bool [Stop](#) ()
Stop all moving actuators
- void [WaitForEndOfMove](#) (short nAxis)
Blocking function that completes once current actuator motion completes

Static Public Attributes

- static short [PORT_TYPE](#) = 2
Enum constant identifying controller port as an ethernet connection
- static short [PORT_ID](#) = 3240
Port id used to connect to controller
- static string [IP](#) = "192.168.0.250"
Static IP address of controller
- static short [NUMBER_AXES](#) = 8
Number of axes on controller
- static short [ATYPE](#) = 43
Enum value identifying a step-direction stepper driver type
- static string [] [AX_PROPERTIES](#) = { "ATYPE", "P_GAIN", "I_GAIN", "D_GAIN", "OV_GAIN", "VFF_GAIN", "UNITS", "SPEED", "ACCEL", "DECEL", "CREEP", "JOGSPEED", "FE_LIMIT", "DAC", "SERVO", "REP_DISTANCE", "FWD_IN", "REV_IN", "DATUM_IN", "FS_LIMIT", "RS_LIMIT", "MTYPE", "NTYPE", "MPOS", "DPOS", "FE", "AXISSTATUS" }
Property names accessible for each motor

Properties

- bool [Open](#) [get]
Indicates whether or not controller is connected and port is opened

5.34.1 Detailed Description

Class representing Trio stepper motor controller

5.34.2 Constructor & Destructor Documentation

5.34.2.1 TrioController()

```
RCCM.TrioController.TrioController (
    AxTrioPC axTrioPC )
```

Connect to and initialize Trio controller

Parameters

<i>axTrioPC</i>	Trio ActiveX control
-----------------	----------------------

5.34.3 Member Function Documentation

5.34.3.1 GetAllAxisProperties()

```
double [ ] RCCM.TrioController.GetAllAxisProperties (
    short nAxis )
```

Get all axis property values

Parameters

<i>nAxis</i>	Number (0-7) of port where axis is connected to trio controller
--------------	---

Returns

Array of property values with indices corresponding to [TrioController.AX_PROPERTIES](#)

5.34.3.2 GetAxisProperty()

```
double RCCM.TrioController.GetAxisProperty (
    string property,
    short nAxis )
```

Get a specified property of a motor

Parameters

<i>property</i>	Name of property to check
<i>nAxis</i>	Number (0-7) of port where axis is connected to trio controller

Returns

Specified property value

5.34.3.3 GetProperty()

```
double RCCM.TrioController.GetProperty (
    string property )
```

Get property value (could be axis or controller property)

Parameters

<i>property</i>	Property name
-----------------	---------------

Returns

Current property value

5.34.3.4 isMoving()

```
bool RCCM.TrioController.isMoving (
    short nAxis )
```

Check if an axis is currently moving

Parameters

<i>nAxis</i>	Number (0-7) of port where axis is connected to trio controller
--------------	---

Returns

True if axis is performing a motion

5.34.3.5 Jog()

```
bool RCCM.TrioController.Jog (
    bool fwd,
    short nAxis )
```

Begin moving an actuator continuously

Parameters

<i>fwd</i>	Flag to indicate if actuator should move forward or backward
<i>nAxis</i>	Number (0-7) of port where axis is connected to trio controller

Returns

True if command was sent successfully

5.34.3.6 JogStop()

```
bool RCCM.TrioController.JogStop (
    short nAxis )
```

Stop continuous actuator motion

Parameters

<i>nAxis</i>	Number (0-7) of port where axis is connected to trio controller
--------------	---

Returns

True if command was sent successfully

5.34.3.7 MoveAbs()

```
bool RCCM.TrioController.MoveAbs (
    short nAxis,
    double pos )
```

Move a specified actuator to a new coordinate

Parameters

<i>nAxis</i>	Number (0-7) of port where axis is connected to trio controller
<i>pos</i>	New position of axis

Returns

True if command was sent successfully

5.34.3.8 MoveRel()

```
bool RCCM.TrioController.MoveRel (
    short nAxis,
    double pos )
```

Move a specified distance from current actuator position

Parameters

<i>nAxis</i>	Number (0-7) of port where axis is connected to trio controller
<i>pos</i>	Distance to move

Returns

True if command was sent successfully

5.34.3.9 SetAxisProperty()

```
bool RCCM.TrioController.SetAxisProperty (
    string property,
    double value,
    short nAxis )
```

Set a specified property of a motor

Parameters

<i>property</i>	Name of property to check
<i>value</i>	New value of property
<i>nAxis</i>	Number (0-7) of port where axis is connected to trio controller

Returns

True if value was set successfully

5.34.3.10 Stop()

```
bool RCCM.TrioController.Stop ( )
```

Stop all moving actuators

Returns

True if command was sent successfully

5.34.3.11 WaitForEndOfMove()

```
void RCCM.TrioController.WaitForEndOfMove (
    short nAxis )
```

Blocking function that completes once current actuator motion completes

Parameters

<i>nAxis</i>	Number (0-7) of port where axis is connected to trio controller
--------------	---

5.34.3.12 Zero()

```
void RCCM.TrioController.Zero (
    short nAxis )
```

Set current actuator position as 0 and clear errors

Parameters

<i>nAxis</i>	Number (0-7) of port where axis is connected to trio controller
--------------	---

5.34.4 Member Data Documentation

5.34.4.1 ATYPE

```
short RCCM.TrioController.ATYPE = 43 [static]
```

Enum value identifying a step-direction stepper driver type

5.34.4.2 AX_PROPERTIES

```
string [] RCCM.TrioController.AX_PROPERTIES = { "ATYPE", "P_GAIN", "I_GAIN", "D_GAIN", "OV↔
GAIN", "VFF_GAIN", "UNITS", "SPEED", "ACCEL", "DECEL", "CREEP", "JOGSPEED", "FE_LIMIT", "DAC",
"SERVO", "REP_DIST", "FWD_IN", "REV_IN", "DATUM_IN", "FS_LIMIT", "RS_LIMIT", "MTYPE", "NTYPE",
"MPOS", "DPOS", "FE", "AXISSTATUS" } [static]
```

Property names accessible for each motor

5.34.4.3 IP

```
string RCCM.TrioController.IP = "192.168.0.250" [static]
```

Static IP address of controller

5.34.4.4 NUMBER_AXES

```
short RCCM.TrioController.NUMBER_AXES = 8 [static]
```

Number of axes on controller

5.34.4.5 PORT_ID

```
short RCCM.TrioController.PORT_ID = 3240 [static]
```

Port id used to connect to controller

5.34.4.6 PORT_TYPE

```
short RCCM.TrioController.PORT_TYPE = 2 [static]
```

Enum constant identifying controller port as an ethernet connection

5.34.5 Property Documentation

5.34.5.1 Open

```
bool RCCM.TrioController.Open [get]
```

Indicates whether or not controller is connected and port is opened


The documentation for this class was generated from the following file:

- RCCM/TrioController.cs

5.35 RCCM.TrioStepperMotor Class Reference

Object representing a physical motor controlled through Trio controller

Inheritance diagram for RCCM.TrioStepperMotor:



Public Member Functions

- [TrioStepperMotor](#) ([TrioController](#) controller, short axisNum)
Create a trio motor object. [Settings](#) are not initialized in this function
- override void [Jog](#) (bool fwd)
Begin moving this actuator continuously
- override void [JogStop](#) ()
Stop moving axis continuously
- override bool [Initialize](#) ()
Initialize status variables of superclass [Motor](#)
- override double [SetPos](#) (double cmd)
Set the command position of the motor. After calling this method, [getPos\(\)](#) will return cmd
- override double [MoveRel](#) (double dist)
Set the command position of the motor. After calling this method, [getPos\(\)](#) will return cmd
- override double [GetPos](#) ()
Get motor position. This is accessed using the MPOS axis property
- override void [Zero](#) ()
Set current actuator position as zero and clear errors
- override Dictionary< string, double > [GetAllProperties](#) ()
Get all axis property values in a dictionary
- override double [GetProperty](#) (string property)
Get a specified axis property
- override bool [SetProperty](#) (string property, double value)
Set axis property
- override void [WaitForEndOfMove](#) ()
Blocking function that completes when current actuator motion ends

Static Public Attributes

- static Dictionary< string, string > [TRIO_PROPERTY_MAP](#)
Dictionary mapping settings file properties to corresponding Trio axis properties

Additional Inherited Members

5.35.1 Detailed Description

Object representing a physical motor controlled through Trio controller

5.35.2 Constructor & Destructor Documentation

5.35.2.1 TrioStepperMotor()

```
RCCM.TrioStepperMotor.TrioStepperMotor (
    TrioController controller,
    short axisNum )
```

Create a trio motor object. [Settings](#) are not initialized in this function

Parameters

<i>controller</i>	
<i>axisNum</i>	

5.35.3 Member Function Documentation

5.35.3.1 GetAllProperties()

```
override Dictionary<string, double> RCCM.TrioStepperMotor.GetAllProperties ( ) [virtual]
```

Get all axis property values in a dictionary

Returns

A dictionary of property name, value pairs

Implements [RCCM.Motor](#).

5.35.3.2 GetPos()

```
override double RCCM.TrioStepperMotor.GetPos ( ) [virtual]
```

Get motor position. This is accessed using the MPOS axis property

Returns

Current position

Implements [RCCM.Motor](#).

5.35.3.3 GetProperty()

```
override double RCCM.TrioStepperMotor.GetProperty (
    string property ) [virtual]
```

Get a specified axis property

Parameters

<i>property</i>	Property name
-----------------	---------------

Returns

Current property value

Reimplemented from [RCCM.Motor](#).

5.35.3.4 Initialize()

```
override bool RCCM.TrioStepperMotor.Initialize ( ) [virtual]
```

Initialize status variables of superclass [Motor](#)

Returns

Initialization status of motor

Implements [RCCM.Motor](#).

5.35.3.5 Jog()

```
override void RCCM.TrioStepperMotor.Jog (
    bool fwd ) [virtual]
```

Begin moving this actuator continuously

Parameters

<i>fwd</i>	Flag indicating direction of motion. True corresponds to forward
------------	--

Implements [RCCM.Motor](#).

5.35.3.6 JogStop()

```
override void RCCM.TrioStepperMotor.JogStop ( ) [virtual]
```

Stop moving axis continuously

Implements [RCCM.Motor](#).

5.35.3.7 MoveRel()

```
override double RCCM.TrioStepperMotor.MoveRel (
    double dist ) [virtual]
```

Set the command position of the motor. After calling this method, `getPos()` will return `cmd`

Parameters

<i>dist</i>	New command position
-------------	----------------------

Returns

The previous commanded position

Implements [RCCM.Motor](#).

5.35.3.8 SetPos()

```
override double RCCM.TrioStepperMotor.SetPos (  
    double cmd ) [virtual]
```

Set the command position of the motor. After calling this method, getPos() will return cmd

Parameters

<i>cmd</i>	New command position
------------	----------------------

Returns

The new commanded position

Implements [RCCM.Motor](#).

5.35.3.9 SetProperty()

```
override bool RCCM.TrioStepperMotor.SetProperty (  
    string property,  
    double value ) [virtual]
```

Set axis property

Parameters

<i>property</i>	Property name
<i>value</i>	New property value

Returns

True if property was set successfully

Reimplemented from [RCCM.Motor](#).

5.35.3.10 WaitForEndOfMove()

```
override void RCCM.TrioStepperMotor.WaitForEndOfMove ( ) [virtual]
```

Blocking function that completes when current actuator motion ends

Implements [RCCM.Motor](#).

5.35.3.11 Zero()

```
override void RCCM.TrioStepperMotor.Zero ( ) [virtual]
```

Set current actuator position as zero and clear errors

Reimplemented from [RCCM.Motor](#).

5.35.4 Member Data Documentation

5.35.4.1 TRIO_PROPERTY_MAP

```
Dictionary<string, string> RCCM.TrioStepperMotor.TRIO_PROPERTY_MAP [static]
```

Initial value:

```
= new Dictionary<string, string>{
    { "enabled", "AXIS_ENABLE" },
    { "microstep per mm", "UNITS" },
    { "velocity", "SPEED" },
    { "jog speed", "JOGSPEED" },
    { "acceleration", "ACCEL" },
    { "deceleration", "DECEL" },
    { "low position limit", "AXIS_RS_LIMIT" },
    { "high position limit", "AXIS_FS_LIMIT" },
    { "home", "" }
}
```

Dictionary mapping settings file properties to corresponding Trio axis properties


The documentation for this class was generated from the following file:

- [RCCM/TrioStepperMotor.cs](#)

5.36 RCCM.TrioStepperZMotor Class Reference

Actuator controlled through trio controller that adjusts its position based on distance sensor input

Inheritance diagram for [RCCM.TrioStepperZMotor](#):



Public Member Functions

- [TrioStepperZMotor](#) ([TrioController](#) controller, short [axisNum](#), [RCCMSystem](#) rccm, [RCCMStage](#) stage)
Create a controlled z actuator
- override double [GetPos](#) ()
Get actuator height above panel
- override double [SetPos](#) (double cmdHeight)
Set current position of actuator (independent of feedback property value)
- override double [MoveRel](#) (double dist)
Move command position a specified distance from current
- override bool [Initialize](#) ()
Does nothing
- override Dictionary< string, double > [GetAllProperties](#) ()
Get all property values in a dictionary
- override double [GetProperty](#) (string property)
Get a specified property value
- override bool [SetProperty](#) (string property, double value)
Set a property value
- override void [WaitForEndOfMove](#) ()
Blocking function that completes when actuator motion ends
- override void [Jog](#) (bool fwd)
Pauses active adjustment of actuator and begins moving axis continuously
- override void [JogStop](#) ()
Stop jogging actuator and resume adjustment thread
- override void [Zero](#) ()
Set current position of actuator as 0 and clear any errors
- override double [GetActuatorPos](#) ()
Get position of actuator from end of travel
- void [Pause](#) ()
Pause active height adjustment
- void [Resume](#) ()
Unpause active height adjustment
- override void [Terminate](#) ()
Stop background adjustment thread

Static Public Attributes

- static Dictionary< string, string > [TRIO_PROPERTY_MAP](#)
Dictionary mapping settings property names to their corresponding Trio axis property
- static long [UPDATE_PERIOD](#) = (long)Program.Settings.json["distance sensor"]["z position update period"]
Time in milliseconds between commands sent to controller
- static double [ERROR](#) = (double)Program.Settings.json["distance sensor"]["max height error"]
Maximum allowable error between command height and measured height before axis is adjusted
- static double [PGAIN](#) = 0.5
Gain multiplying position error to determine much correction actuator should do

Protected Attributes

- [TrioController controller](#)
RCCM Trio controller object
- short [axisNum](#)
Number of port where this axis is connected to Trio controller
- Func< double > [height](#)
Function reference for getting height of actuator above panel
- Func< double > [minPosition](#)
Function reference for computing lowest position that axis should move to from current position on panel
- double [commandHeight](#)
Current desired height above panel
- BackgroundWorker [bw](#)
Background worker for sending movement commands
- AutoResetEvent [adjustThreadExited](#)
Event for when background thread exits
- bool [adjust](#)
Flag indicating if background thread should continue running
- bool [adjustThreadPaused](#)
Flag indicating if actuator should be actively trying to match height to command height

Additional Inherited Members

5.36.1 Detailed Description

Actuator controlled through trio controller that adjusts its position based on distance sensor input

5.36.2 Constructor & Destructor Documentation

5.36.2.1 TrioStepperZMotor()

```
RCCM.TrioStepperZMotor.TrioStepperZMotor (
    TrioController controller,
    short axisNum,
    RCCMSystem rccm,
    RCCMStage stage )
```

Create a controlled z actuator

Parameters

<i>controller</i>	RCCM Trio controller object
<i>axisNum</i>	Number of port where axis is connected to Trio controller
<i>rccm</i>	The RCCM object
<i>stage</i>	Enum value of the set of fine actuators containing this actuator

5.36.3 Member Function Documentation

5.36.3.1 GetActuatorPos()

```
override double RCCM.TrioStepperZMotor.GetActuatorPos ( ) [virtual]
```

Get position of actuator from end of travel

Returns

Current actuator position

Reimplemented from [RCCM.Motor](#).

5.36.3.2 GetAllProperties()

```
override Dictionary<string, double> RCCM.TrioStepperZMotor.GetAllProperties ( ) [virtual]
```

Get all property values in a dictionary

Returns

Dictionary of property name, value pairs

Implements [RCCM.Motor](#).

5.36.3.3 GetPos()

```
override double RCCM.TrioStepperZMotor.GetPos ( ) [virtual]
```

Get actuator height above panel

Returns

Current height of actuator above panel

Implements [RCCM.Motor](#).

5.36.3.4 GetProperty()

```
override double RCCM.TrioStepperZMotor.GetProperty (
    string property ) [virtual]
```

Get a specified property value

Parameters

<i>property</i>	Name of property
-----------------	------------------

Returns

Current property value

Reimplemented from [RCCM.Motor](#).

5.36.3.5 Initialize()

```
override bool RCCM.TrioStepperZMotor.Initialize ( ) [virtual]
```

Does nothing

Returns

True if actuator is enabled

Implements [RCCM.Motor](#).

5.36.3.6 Jog()

```
override void RCCM.TrioStepperZMotor.Jog (
    bool fwd ) [virtual]
```

Pauses active adjustment of actuator and begins moving axis continuously

Parameters

<i>fwd</i>	Flag indicating direction of move
------------	-----------------------------------

Implements [RCCM.Motor](#).

5.36.3.7 JogStop()

```
override void RCCM.TrioStepperZMotor.JogStop ( ) [virtual]
```

Stop jogging actuator and resume adjustment thread

Implements [RCCM.Motor](#).

5.36.3.8 MoveRel()

```
override double RCCM.TrioStepperZMotor.MoveRel (
    double dist ) [virtual]
```

Move command position a specified distance from current

Parameters

<i>dist</i>	Distance to move
-------------	------------------

Returns

Last command position

Implements [RCCM.Motor](#).

5.36.3.9 Pause()

```
void RCCM.TrioStepperZMotor.Pause ( )
```

Pause active height adjustment

5.36.3.10 Resume()

```
void RCCM.TrioStepperZMotor.Resume ( )
```

Unpause active height adjustment

5.36.3.11 SetPos()

```
override double RCCM.TrioStepperZMotor.SetPos (
    double cmdHeight ) [virtual]
```

Set current position of actuator (independent of feedback property value)

Parameters

<i>cmdHeight</i>	New command position of actuator
------------------	----------------------------------

Returns

Coerced command position

Implements [RCCM.Motor](#).

5.36.3.12 SetProperty()

```
override bool RCCM.TrioStepperZMotor.SetProperty (
    string property,
    double value ) [virtual]
```

Set a property value

Parameters

<i>property</i>	Property name
<i>value</i>	New property value

Returns

True if property was set succesfully

Reimplemented from [RCCM.Motor](#).

5.36.3.13 Terminate()

```
override void RCCM.TrioStepperZMotor.Terminate ( ) [virtual]
```

Stop background adjustment thread

Reimplemented from [RCCM.Motor](#).

5.36.3.14 WaitForEndOfMove()

```
override void RCCM.TrioStepperZMotor.WaitForEndOfMove ( ) [virtual]
```

Blocking function that completes when actuator motion ends

Implements [RCCM.Motor](#).

5.36.3.15 Zero()

```
override void RCCM.TrioStepperZMotor.Zero ( ) [virtual]
```

Set current position of actuator as 0 and clear any errors

Reimplemented from [RCCM.Motor](#).

5.36.4 Member Data Documentation

5.36.4.1 adjust

`bool RCCM.TrioStepperZMotor.adjust [protected]`

Flag indicating if background thread should continue running

5.36.4.2 adjustThreadExited

`AutoResetEvent RCCM.TrioStepperZMotor.adjustThreadExited [protected]`

Event for when background thread exits

5.36.4.3 adjustThreadPaused

`bool RCCM.TrioStepperZMotor.adjustThreadPaused [protected]`

Flag indicating if actuator should be actively trying to match height to command height

5.36.4.4 axisNum

`short RCCM.TrioStepperZMotor.axisNum [protected]`

Number of port where this axis is connected to Trio controller

5.36.4.5 bw

`BackgroundWorker RCCM.TrioStepperZMotor.bw [protected]`

Background worker for sending movement commands

5.36.4.6 commandHeight

`double RCCM.TrioStepperZMotor.commandHeight [protected]`

Current desired height above panel

5.36.4.7 controller

`TrioController RCCM.TrioStepperZMotor.controller [protected]`

[RCCM](#) Trio controller object

5.36.4.8 ERROR

```
double RCCM.TrioStepperZMotor.ERROR = (double)Program.Settings.json["distance sensor"]["max
height error"] [static]
```

Maximum allowable error between command height and measured height before axis is adjusted

5.36.4.9 height

```
Func<double> RCCM.TrioStepperZMotor.height [protected]
```

Function reference for getting height of actuator above panel

5.36.4.10 minPosition

```
Func<double> RCCM.TrioStepperZMotor.minPosition [protected]
```

Function reference for computing lowest position that axis should move to from current position on panel

5.36.4.11 PGAIN

```
double RCCM.TrioStepperZMotor.PGAIN = 0.5 [static]
```

Gain multiplying position error to determine much correction actuator should do

5.36.4.12 TRIO_PROPERTY_MAP

```
Dictionary<string, string> RCCM.TrioStepperZMotor.TRIO_PROPERTY_MAP [static]
```

Initial value:

```
= new Dictionary<string, string>{
    { "enabled", "AXIS_ENABLE" },
    { "microstep per mm", "UNITS" },
    { "velocity", "SPEED" },
    { "jog speed", "JOGSPEED" },
    { "acceleration", "ACCEL" },
    { "deceleration", "DECEL" },
    { "low position limit", "AXIS_RS_LIMIT" },
    { "high position limit", "AXIS_FS_LIMIT" },
    { "home", "" },
    { "feedback", "" }
}
```

Dictionary mapping settings property names to their corresponding Trio axis property

5.36.4.13 UPDATE_PERIOD

```
long RCCM.TrioStepperZMotor.UPDATE_PERIOD = (long)Program.Settings.json["distance sensor"]["z
position update period"] [static]
```

Time in milliseconds between commands sent to controller


The documentation for this class was generated from the following file:

- RCCM/TrioStepperZMotor.cs

5.37 RCCM.VirtualMotor Class Reference

Virtual representation of motor for use when motor is not connected

Inheritance diagram for RCCM.VirtualMotor:



Public Member Functions

- override double [GetPos](#) ()
Get motor position. For a virtual motor, this is simply the last commanded position
- override double [SetPos](#) (double cmd)
Set the command position of the motor. After calling this method, getPos() will return cmd
- override double [MoveRel](#) (double dist)
Move the motor a specified distance
- override bool [Initialize](#) ()
Initialize status variables of superclass [Motor](#)
- override Dictionary< string, double > [GetAllProperties](#) ()
Get all property value pairs for this motor in a dictionary
- override void [WaitForEndOfMove](#) ()
Since move is applied instantaneously, no waiting necessary
- override void [Jog](#) (bool fwd)
Pretend to jog this motor lol
- override void [JogStop](#) ()
Pretend to stop jogging this motor lol

Additional Inherited Members

5.37.1 Detailed Description

Virtual representation of motor for use when motor is not connected

5.37.2 Member Function Documentation

5.37.2.1 GetAllProperties()

```
override Dictionary<string, double> RCCM.VirtualMotor.GetAllProperties ( ) [virtual]
```

Get all property value pairs for this motor in a dictionary

Returns

Dictionary of property value pairs

Implements [RCCM.Motor](#).

5.37.2.2 GetPos()

```
override double RCCM.VirtualMotor.GetPos ( ) [virtual]
```

Get motor position. For a virtual motor, this is simply the last commanded position

Returns

Current position

Implements [RCCM.Motor](#).

5.37.2.3 Initialize()

```
override bool RCCM.VirtualMotor.Initialize ( ) [virtual]
```

Initialize status variables of superclass [Motor](#)

Returns

Initialization status of motor

Implements [RCCM.Motor](#).

5.37.2.4 Jog()

```
override void RCCM.VirtualMotor.Jog (
    bool fwd ) [virtual]
```

Pretend to jog this motor lol

Parameters

<i>fwd</i>	Direction of jog - forward if true
------------	------------------------------------

Implements [RCCM.Motor](#).

5.37.2.5 JogStop()

```
override void RCCM.VirtualMotor.JogStop ( ) [virtual]
```

Pretend to stop jogging this motor lol

Implements [RCCM.Motor](#).

5.37.2.6 MoveRel()

```
override double RCCM.VirtualMotor.MoveRel (
    double dist ) [virtual]
```

Move the motor a specified distance

Parameters

<i>dist</i>	Distance to move
-------------	------------------

Returns

The previous commanded position

Implements [RCCM.Motor](#).

5.37.2.7 SetPos()

```
override double RCCM.VirtualMotor.SetPos (
    double cmd ) [virtual]
```

Set the command position of the motor. After calling this method, `getPos()` will return `cmd`

Parameters

<i>cmd</i>	New command position
------------	----------------------

Returns

The new commanded position

Implements [RCCM.Motor](#).

5.37.2.8 WaitForEndOfMove()

```
override void RCCM.VirtualMotor.WaitForEndOfMove ( ) [virtual]
```

Since move is applied instantaneously, no waiting necessary

Implements [RCCM.Motor](#).


The documentation for this class was generated from the following file:

- [RCCM/VirtualMotor.cs](#)

5.38 RCCM.WFOV Class Reference

Class representing DMK Z12G445 camera for the [RCCM WFOV](#)

Inheritance diagram for RCCM.WFOV:

**Public Member Functions**

- [WFOV](#) (string name)
Create [WFOV](#) camera from configuration file
- bool [Initialize](#) (ICImagingControl ic)
Connect to camera. Will fail if configuration file referred to invalid or disconnected camera
- void [Start](#) ()
Begin displaying live image
- void [Stop](#) ()
Stop displaying live image. Will also cease video recording, if active
- void [Snap](#) (string filename)
Capture live image to file
- void [Record](#) (string filename)
Start recording video to specified path
- void [StopRecord](#) ()
Stop recording video. Will resume live display after stopping recording
- void [SetScale](#) (RCCMSystem rccm, double scale)
Set image scale and save current height, zoom, and focus
- bool [CheckFOV](#) (RCCMSystem rccm)
Check if measurement conditions match calibration conditions
- void [EditProperties](#) ()
Show device property dialog <warning>Will cause device to crash if "Cancel" button is pressed from property dialog</warning>
- int [AutoFocus](#) ()
Activate built-in camera autofocus. Requires 2 second sleep to allow autofocus to complete

Static Public Attributes

- static int [IMG_HEIGHT](#) = 960
Height in pixels of image
- static int [IMG_WIDTH](#) = 1280
Width in pixels of image

Protected Attributes

- [ICImagingControl](#) [ic](#)
Imaging user control for displaying the live image
- [VCDSimpleProperty](#) [VCDProp](#)
Camera properties accessor

Properties

- bool [Available](#) [get]
Flag to indicate connection status of [WFOV](#) camera
- double [Scale](#) [get, protected set]
Camera microns / pixel calibration
- double [Height](#) [get]
Height in mm of image
- double [Width](#) [get]
Height in mm of image
- int [Zoom](#) [get, set]
Zoom level of the camera, an integer between 0 and 100
- int [Focus](#) [get, set]
Focal distance of the camera, roughly equating to distance in mm
- int [FocusMin](#) [get]
Minimum focal distance of the camera
- int [FocusMax](#) [get]
Maximum focal distance of the camera
- int [ZoomMin](#) [get]
Minimum zoom level of the camera
- int [ZoomMax](#) [get]
Maximum zoom level of the camera
- bool [Recording](#) [get]
Flag to indicate if a video is being recorded
- string [configFile](#) [get, set]
File path to configuration file from which camera is initialized
- double [CalibrationHeight](#) [get, protected set]
File path to configuration file from which camera is initialized
- double [CalibrationZoom](#) [get, protected set]
File path to configuration file from which camera is initialized
- double [CalibrationFocus](#) [get, protected set]
File path to configuration file from which camera is initialized

5.38.1 Detailed Description

Class representing DMK Z12G445 camera for the [RCCM WFOV](#)

5.38.2 Constructor & Destructor Documentation

5.38.2.1 WFOV()

```
RCCM.WFOV.WFOV (
    string name )
```

Create [WFOV](#) camera from configuration file

Parameters

<i>name</i>	Name of camera in settings
-------------	----------------------------

5.38.3 Member Function Documentation

5.38.3.1 AutoFocus()

```
int RCCM.WFOV.AutoFocus ( )
```

Activate built-in camera autofocus. Requires 2 second sleep to allow autofocus to complete

Returns

New focus level

5.38.3.2 CheckFOV()

```
bool RCCM.WFOV.CheckFOV (
    RCCMSystem rccm )
```

Check if measurement conditions match calibration conditions

Parameters

<i>rccm</i>	
-------------	--

Returns

True if measurement conditions match calibration

Implements [RCCM.ICamera](#).

5.38.3.3 EditProperties()

```
void RCCM.WFOV.EditProperties ( )
```

Show device property dialog <warning>Will cause device to crash if "Cancel" button is pressed from property dialog</warning>

5.38.3.4 Initialize()

```
bool RCCM.WFOV.Initialize (
    ICImpagingControl ic )
```

Connect to camera. Will fail if configuration file referred to invalid or disconnected camera

Returns

True if initialization is successful

5.38.3.5 Record()

```
void RCCM.WFOV.Record (
    string filename )
```

Start recording video to specified path

Parameters

<i>filename</i>	
-----------------	--

Implements [RCCM.ICamera](#).

5.38.3.6 SetScale()

```
void RCCM.WFOV.SetScale (
    RCCMSystem rccm,
    double scale )
```

Set image scale and save current height, zoom, and focus

Parameters

<i>rccm</i>	
<i>scale</i>	New calibration

Implements [RCCM.ICamera](#).

5.38.3.7 Snap()

```
void RCCM.WFOV.Snap (
    string filename )
```

Capture live image to file

Parameters

<i>filename</i>	Filename to save image to. Should have .png extension
-----------------	---

Implements [RCCM.ICamera](#).

5.38.3.8 Start()

```
void RCCM.WFOV.Start ( )
```

Begin displaying live image

Implements [RCCM.ICamera](#).

5.38.3.9 Stop()

```
void RCCM.WFOV.Stop ( )
```

Stop displaying live image. Will also cease video recording, if active

Implements [RCCM.ICamera](#).

5.38.3.10 StopRecord()

```
void RCCM.WFOV.StopRecord ( )
```

Stop recording video. Will resume live display after stopping recording

Implements [RCCM.ICamera](#).

5.38.4 Member Data Documentation

5.38.4.1 ic

```
ICImagingControl RCCM.WFOV.ic [protected]
```

Imaging user control for displaying the live image

5.38.4.2 IMG_HEIGHT

```
int RCCM.WFOV.IMG_HEIGHT = 960 [static]
```

Height in pixels of image

5.38.4.3 IMG_WIDTH

```
int RCCM.WFOV.IMG_WIDTH = 1280 [static]
```

Width in pixels of image

5.38.4.4 VCDProp

```
VCDSimpleProperty RCCM.WFOV.VCDProp [protected]
```

Camera properties accessor

5.38.5 Property Documentation

5.38.5.1 Available

```
bool RCCM.WFOV.Available [get]
```

Flag to indicate connection status of [WFOV](#) camera

5.38.5.2 CalibrationFocus

```
double RCCM.WFOV.CalibrationFocus [get], [protected set]
```

File path to configuration file from which camera is initialized

5.38.5.3 CalibrationHeight

```
double RCCM.WFOV.CalibrationHeight [get], [protected set]
```

File path to configuration file from which camera is initialized

5.38.5.4 CalibrationZoom

```
double RCCM.WFOV.CalibrationZoom [get], [protected set]
```

File path to configuration file from which camera is initialized

5.38.5.5 configFile

```
string RCCM.WFOV.configFile [get], [set]
```

File path to configuration file from which camera is initialized

5.38.5.6 Focus

```
int RCCM.WFOV.Focus [get], [set]
```

Focal distance of the camera, roughly equating to distance in mm

5.38.5.7 FocusMax

```
int RCCM.WFOV.FocusMax [get]
```

Maximum focal distance of the camera

5.38.5.8 FocusMin

```
int RCCM.WFOV.FocusMin [get]
```

Minimum focal distance of the camera

5.38.5.9 Height

```
double RCCM.WFOV.Height [get]
```

Height in mm of image

5.38.5.10 Recording

```
bool RCCM.WFOV.Recording [get]
```

Flag to indicate if a video is being recorded

5.38.5.11 Scale

```
double RCCM.WFOV.Scale [get], [protected set]
```

Camera microns / pixel calibration

5.38.5.12 Width

```
double RCCM.WFOV.Width [get]
```

Height in mm of image

5.38.5.13 Zoom

```
int RCCM.WFOV.Zoom [get], [set]
```

Zoom level of the camera, an integer between 0 and 100

5.38.5.14 ZoomMax

```
int RCCM.WFOV.ZoomMax [get]
```

Maximum zoom level of the camera

5.38.5.15 ZoomMin

```
int RCCM.WFOV.ZoomMin [get]
```

Minimum zoom level of the camera


The documentation for this class was generated from the following file:

- RCCM/WFOV.cs

5.39 RCCM.UI.WFOVViewForm Class Reference

Form for displaying [WFOV](#) live image and measurement overlay

Inheritance diagram for RCCM.UI.WFOVViewForm:



Public Member Functions

- [WFOVViewForm](#) ([RCCMSystem](#) rccm, [WFOV](#) camera, [ObservableCollection](#)< [MeasurementSequence](#) > cracks)
Create form and initialize given camera
- void [createSegment](#) ()
Create segment that was being drawn by user with mouse input. This will add a point or segment to the active [MeasurementSequence](#)
- void [moveDrawnLineEnd](#) (int x, int y, int w, int h)
Move the end point of the line segment that user is currently drawing
- void [createDrawnLine](#) (int x, int y, int w, int h)
Begin drawing new segment in active [MeasurementSequence](#) from user mouse input
- void [createPoint](#) (int x, int y, int w, int h)
Create new point in active measurement sequence at mouse location

Protected Member Functions

- override void [Dispose](#) (bool disposing)
Clean up any resources being used.

Protected Attributes

- readonly [RCCMSystem](#) rccm
The [RCCM](#) system object. Used for calculating [WFOV](#) position
- readonly [ObservableCollection](#)< [MeasurementSequence](#) > cracks
List of cracks that are being measured
- readonly [WFOV](#) camera
[WFOV](#) camera that is displayed by this window
- [RCCMStage](#) stage
Parent stage of this camera
- [PointF](#) drawnLineStart
Point where line user is drawing begins
- [PointF](#) drawnLineEnd
Point where line user is drawing ends

Properties

- int [ActiveIndex](#) [get, set]
Currently selected crack index. The selected crack will be edited by other controls
- int [ActivePoint](#) [get, set]
Currently selected point in *ListPoints*. This point is indicated in the image display
- float [displayScale](#) [get]
Ratio of picture box size to actual *NFOV* image dimensions
- bool [Drawing](#) [get]
Indicates whether or not user is drawing a line with mouse

5.39.1 Detailed Description

Form for displaying [WFOV](#) live image and measurement overlay

5.39.2 Constructor & Destructor Documentation

5.39.2.1 WFOVViewForm()

```
RCCM.UI.WFOVViewForm.WFOVViewForm (
    RCCMSystem rccm,
    WFOV camera,
    ObservableCollection< MeasurementSequence > cracks )
```

Create form and initialize given camera

Parameters

<i>rccm</i>	Reference to the RCCM object
<i>camera</i>	Camera to be displayed
<i>cracks</i>	Reference to the list of all measurement sequences

5.39.3 Member Function Documentation

5.39.3.1 createDrawnLine()

```
void RCCM.UI.WFOVViewForm.createDrawnLine (
    int x,
    int y,
    int w,
    int h )
```

Begin drawing new segment in active [MeasurementSequence](#) from user mouse input

Parameters

<i>x</i>	Mouse x location in pixels
<i>y</i>	Mouse y location in pixels
<i>w</i>	Canvas width in pixels
<i>h</i>	Canvas height in pixels

5.39.3.2 createPoint()

```
void RCCM.UI.WFOVViewForm.createPoint (
    int x,
    int y,
    int w,
    int h )
```

Create new point in active measurement sequence at mouse location

Parameters

<i>x</i>	Mouse x location in pixels
<i>y</i>	Mouse y location in pixels
<i>w</i>	Canvas width in pixels
<i>h</i>	Canvas height in pixels

5.39.3.3 createSegment()

```
void RCCM.UI.WFOVViewForm.createSegment ( )
```

Create segment that was being drawn by user with mouse input. This will add a point or segment to the active [MeasurementSequence](#)

5.39.3.4 Dispose()

```
override void RCCM.UI.WFOVViewForm.Dispose (
    bool disposing ) [protected]
```

Clean up any resources being used.

Parameters

<i>disposing</i>	true if managed resources should be disposed; otherwise, false.
------------------	---

5.39.3.5 moveDrawnLineEnd()

```
void RCCM.UI.WFOVViewForm.moveDrawnLineEnd (
    int x,
    int y,
    int w,
    int h )
```

Move the end point of the line segment that user is currently drawing

Parameters

<i>x</i>	Mouse x location in pixels
<i>y</i>	Mouse y location in pixels
<i>w</i>	Canvas width in pixels
<i>h</i>	Canvas height in pixels

5.39.4 Member Data Documentation

5.39.4.1 camera

```
readonly WFOV RCCM.UI.WFOVViewForm.camera [protected]
```

[WFOV](#) camera that is displayed by this window

5.39.4.2 cracks

```
readonly ObservableCollection<MeasurementSequence> RCCM.UI.WFOVViewForm.cracks [protected]
```

List of cracks that are being measured

5.39.4.3 drawnLineEnd

```
PointF RCCM.UI.WFOVViewForm.drawnLineEnd [protected]
```

Point where line user is drawing ends

5.39.4.4 drawnLineStart

```
PointF RCCM.UI.WFOVViewForm.drawnLineStart [protected]
```

Point where line user is drawing begins

5.39.4.5 rccm

readonly [RCCMSystem](#) RCCM.UI.WFOVViewForm.rccm [protected]

The [RCCM](#) system object. Used for calculating [WFOV](#) position

5.39.4.6 stage

[RCCMStage](#) RCCM.UI.WFOVViewForm.stage [protected]

Parent stage of this camera

5.39.5 Property Documentation

5.39.5.1 ActiveIndex

int RCCM.UI.WFOVViewForm.ActiveIndex [get], [set], [protected]

Currently selected crack index. The selected crack will be edited by other controls

5.39.5.2 ActivePoint

int RCCM.UI.WFOVViewForm.ActivePoint [get], [set], [protected]

Currently selected point in ListPoints. This point is indicated in the image display

5.39.5.3 displayScale

float RCCM.UI.WFOVViewForm.displayScale [get], [protected]

Ratio of picture box size to actual [NFOV](#) image dimensions

5.39.5.4 Drawing

bool RCCM.UI.WFOVViewForm.Drawing [get], [protected]

Indicates whether or not user is drawing a line with mouse

The documentation for this class was generated from the following files:

- [RCCM/UI/WFOVViewForm.cs](#)
- [RCCM/UI/WFOVViewForm.Designer.cs](#)